Calhoun
Institutional Archive of the Naval Postgraduate School

**Calhoun: The NPS Institutional Archive**

**DSpace Repository**

Theses and Dissertations | 1. Thesis and Dissertation Collection, all items

1972

# Towards an English language interactive simulation system

Clapper, Joseph Leon; Nelson, Kenneth Stanley

http://hdl.handle.net/10945/16412

This publication is a work of the U.S. Government as defined in Title 17, United States Code, Section 101. Copyright protection is not available for this work in the United States.

*Downloaded from NPS Archive: Calhoun*

DUDLEY KNOX LIBRARY

Calhoun is the Naval Postgraduate School's public access digital repository for research materials and institutional publications created by the NPS community. Calhoun is named for Professor of Mathematics Guy K. Calhoun, NPS's first appointed -- and published -- scholarly author.

Dudley Knox Library / Naval Postgraduate School
411 Dyer Road / 1 University Circle
Monterey, California USA 93943

http://www.nps.edu/library

# TOWARDS AN ENGLISH LANGUAGE INTERACTIVE SIMULATION SYSTEM

Joseph Leon Clapper

# NAVAL POSTGRADUATE SCHOOL
## Monterey, California

# THESIS

TOWARDS AN ENGLISH LANGUAGE

INTERACTIVE SIMULATION SYSTEM

by

Joseph Leon Clapper

Kenneth Stanley Nelson

Thesis Advisor: G. E. Heidorn

December 1972

*Approved for public release; distribution unlimited.*

T152950

Towards an English Language

Interactive Simulation System

by

Joseph Leon Clapper
Lieutenant, United States Naval Reserve
B.S., Pennsylvania State University, 1968

and

Kenneth Stanley Nelson
Lieutenant, United States Navy
B.S., Oregon State University, 1966

Submitted in partial fulfillment of the
requirements for the degree of

MASTER OF SCIENCE IN COMPUTER SCIENCE

from the

NAVAL POSTGRADUATE SCHOOL
December 1972

Library
Naval Postgraduate School
Monterey, California 93940

## ABSTRACT

Research at the Naval Postgraduate School has led to the development of a system for producing GPSS simulation programs for simple queuing problems through English language dialogue with an IBM 360/67 computer. This thesis describes work done to give the system the capability to actually perform the simulation and report the results through English language dialogue. A complete sample terminal session is included.

TABLE OF CONTENTS

LIST OF FIGURES

# I. INTRODUCTION

Since the advent of the computer, men have been striving to find easier methods of communicating their problems to the machine. Primitive communication was established by using the language of the machine and conversing at the computer's elementary level. In an effort to narrow the communication gap between man and machine, translators have been developed. These translators - assemblers and compilers - facilitate communication with the computer at a level considerably removed from the machine's language. However, even at this level, man is required to learn a new language in order to converse with his powerful assistant. Although significant advances have been made toward generalized, multi-purpose, higher level languages, considerable effort must be expended to learn and utilize these languages in a problem solving situation. A desirable alternative would be to have the ability to specify the problem directly to the machine in a natural language such as English, and have the machine solve the problem and report the results as requested by the user.

Several research projects have investigated various aspects of natural language interaction between man and computer [1, 2]. Developments in the fields of linguistics and artificial intelligence have served to provide basic conceptual structures for natural language processing. One such development is the theory of stratificational linguistics

proposed by S. M. Lamb [3]. In this theory, language is considered to be a multi-level system of relationships.

A research project is currently being conducted at the Naval Postgraduate School to investigate using natural language man-machine interaction in solving queuing problems by simulation [4]. The system being developed is called NLPQ and is a specific application of a more general system called NLP. This work is based on the concepts of stratificational linguistics and utilizes an entity-attribute-value data structure. Background information on the development of both systems is included in this chapter. A further description of each system is included in Chapter II.

## A. BACKGROUND

The initial work done on the project was the development of the general system NLP or Natural Language Processor. The constituents of this system are a "rule language" and a set of FORTRAN routines which compile and execute statements in the rule language. System monitor functions are also performed by the main routine. The system is implemented on the IBM 360/67 and is executed under control of the CP/CMS time sharing system.

With the basic system established, further research began to produce the rule modules necessary to handle a queuing system application (NLPQ). The form of an internal problem description (IPD) for a queuing problem was decided upon and a set of encoding rules

were written to convert the information contained in an IPD to a GPSS program [5]. Additional encoding rules were added to produce an English text description of the information contained in an IPD [6]. The generality of the English encoding rules also permits their use in other areas involving natural language responses from the computer. A set of English decoding rules was then developed to allow the user to describe his queuing problem to the computer in English. These rules perform the function of processing the input English text to produce the IPD. In addition, they are utilized in handling English language requests from the user.

Further research developed modules which would massage and inspect the IPD for missing or erroneous information before producing a GPSS program [7, 8]. In cases where missing or erroneous information is detected, a request is made to the user to supply or correct the required information. A practical by-product of this research is the capability to enter an English problem description in a question-answer mode.

More recently, a FORTRAN subroutine designed to perform a GPSS-like simulation and a set of encoding rules to initialize the data structure required by this routine were developed [9, 10]. Information contained in the IPD can be manipulated by these rules to produce either a GPSS program or a representation of the queuing problem in the data structure utilized by the simulation routine, or both.

## B. THESIS OBJECTIVE

The objective of the research for this thesis was to integrate the simulation routine and associated rules into the existing NLPQ system to produce an initial version of an interactive simulation system. This required making modifications and extensions to both the simulation routine and several of the existing rule modules.

## C. ORGANIZATION OF THE THESIS

Chapter II of this thesis presents a more detailed discussion of pertinent portions of NLP and NLPQ. Chapter III contains a sample session to illustrate the capabilities of NLPQ in an interactive problem solving situation. The considerations involved in the implementation of the interactive simulation capability are discussed in detail in Chapter IV. Finally, Chapter V presents conclusions and recommendations for further research.

# II. DESCRIPTION OF NLP AND NLPQ

Since the interactive simulation capabilities are integrated with, and rely on, the other components of NLPQ, a description of those modules will be presented in this chapter. First, however, the basic concepts related to an overview of the general system NLP, the data structure utilized, and the rule language will be discussed.

## A. BASIC CONCEPTS

This section is intended to provide a general outline of the basic concepts inherent in NLP and NLPQ. A detailed discussion of this material may be found in Ref. 4.

NLP is composed of a set of FORTRAN routines and a rule language. The main program serves as a monitor and performs certain input/output operations. Subroutines compile statements in the rule language and interpret operations given by the rule statements. An entity-attribute-value data structure is utilized to hold information. The generality and usefulness of this type of data structure has been widely recognized in the fields of simulation programming systems and artificial intelligence.

The entity-attribute-value data structure is well suited for holding several types of information. For example, in the current queuing problem application, information about the various words and concepts related to queuing problems must be maintained. Relations between

words and concepts can be considered to be held in long term memory, since information of this type is necessary to carry on a dialogue about any problem.

Other information about a specific problem being described must be retained for the duration of the problem solving session. Information of this type is obtained through discourse. The problem description input by the user is first processed by the "decoding" rules. These rules serve to convert the information contained in the description to an equivalent internal representation. This type of storage can be considered as short term memory since the system need only retain it for the duration of the specific problem solving session.

Another type of information storage can be considered to be temporary or scratchpad memory. For instance, information about parts of a sentence can be discarded after the sentence has been completely processed. An important aspect of NLP is that all of these types of information are maintained in exactly the same form, i. e., entity-attribute-value. Thus, all types of information can be manipulated in the same fashion.

Rules in the rule language of NLP consist of two parts separated by an arrow. The left part generally specifies conditions which must be satisfied before the rule can be applied. The right part of the rule specifies the actions to be taken when the rule is executed. Various basic elements, known as records, establish the state of the system.

These records carry the types of information mentioned in the preceding paragraphs.

Those records which are used in a scratchpad fashion to create or modify other records are called segment records. The state conditions contained in this type of record are the most frequently tested by the rules. The rules for "decoding" specify the manner in which records are to be created from input character strings. The "encoding" rules describe the inverse conversion from records to character strings. Record-to-record transformations can be accomplished by either type of rule. Thus, the basic system deals with the conversion of information. Information in the form of a natural language character string may be transformed to an internal format, manipulated, and possibly returned to a character string. The modular sets of rules for performing these functions for NLPQ will be considered below. Since the internal problem description (IPD) is the structure to be built by the decoding rules, it will be discussed first.

## B. THE INTERNAL PROBLEM DESCRIPTION

Utilizing the entity-attribute-value data structure previously discussed, the logical structure of the IPD is a set of records which contain information about the current problem being processed by NLPQ. These records represent entities such as physical objects or actions occurring in the problem. These entities have attributes which in turn have values associated with them.

A typical queuing problem sequence involves mobile entities engaging in actions (abstract entities) at various stationary entities. In most cases, each of these entities has attributes of varying complexity with specified values. Each of these records in the IPD is a member of one of seven lists. Actions are members of the action list ('ACTNLIST'), mobile and stationary entities are members of the 'MOBLIST' and 'STALIST', respectively. The other lists are: the distribution list ('DSTRLIST'), the successor descriptor list ('SCSRLIST'), the miscellaneous list ('MISCLIST'), and the unit list ('UNITLIST'). Each of these lists is a "named record". Named records provide the long term memory capability previously described; that is, they contain word and concept information pertinent to the application. These particular list records, however, are used to hold information about a specific problem. As entities are encountered during decoding, records are created and linked into the appropriate lists.

The concept structure created by the named records provides the framework of words and their semantic content necessary for discourse. As such they represent the system's vocabulary and knowledge of the relationships between words and concepts. Using this general knowledge, a "mental image" (the IPD) of the specific problem entered by the user can be obtained. The IPD can be considered to be a specific problem instance in the domain of the queuing conceptual structure.

## C. DECODING THE PROBLEM DESCRIPTION

In NLPQ the decoding rules specify how input text is to be converted into equivalent information in the form of records. This conversion is performed within the framework of the Stratificational Grammar theory. Within this theory several levels (strata) of language structure exist. Three levels have been utilized in the NLPQ application; the morphological, lexological, and the semological levels. The "morphology" is concerned with the manner in which characters are put together to form words. As such, it is highly dependent on the particular language being used. The "lexology" deals with the way in which words are put together to form phrases, clauses, and sentences. Different grammatical orderings required by different languages result in language dependency at this level also. The semological level, however, is concerned with relationships and meanings. Thus elements at this level are relatively language independent. The decoding process then involves applying morphological and lexological rules first in processing the input text. Semological rules are then utilized to develop the structure representing the meaning of the text, the IPD.

The general format of a decoding rule is:

SEGMENT TYPE (COND 1, 2, . . . ) SEGMENT TYPE (COND 1, 2, . . . ) . . .

$\longrightarrow$ SEGMENT TYPE (ACTN 1, 2, . . . )

Thus a decoding rule specifies what to do when a particular series of segment types (satisfying the given conditions) is found while processing

the input text. Rule application results in the creation of the segment type on the right and performance of those actions indicated. The conditions specified on the left side of the rule are known as "condition specifications". The actions performed in creation of the new segment on the right side are known as "creation specifications". Both types of specification elements have access to and can manipulate any information in the system.

An illustration of some of these features can be seen in the following rule from the decoding morphology:

VERBS(ING) I N G $\longrightarrow$ VERBP(SUP(VERBS), PRESPART)

The left part of the rule is made up of four segment types, a verb stem (VERBS) segment and three "character" segments. The condition specification for the verb stem requires that the ING indicator in that segment be "on". Indicators are binary-valued and indicate the presence or absence of certain attributes. The right part of the rule defines the conversion to be made when a series of segment types satisfying the left part is encountered. In this case, a new verb part (VERBP) segment is created which is in the same superset as the verb stem and has a present participle indicator on.

Using this basic scheme, information is extracted from the input text and used to build the IPD. Once the semantic content of the user's dialogue has been transformed to the internal format, it can be manipulated in several ways.

## D. ENCODING FROM THE IPD

Since encoding is basically the inverse process of decoding, encoding rules are essentially the inverse of decoding rules. Information is manipulated from the semological level, through the lexological and morphological strata to a natural language text output. A generalized format for an encoding rule is:

SEGMENT TYPE (COND 1, 2, . . . ) $\longrightarrow$

SEGMENT TYPE (ACTN 1, 2, . . . ) SEGMENT TYPE (ACTN 1, 2, . . . ) . . .

In this case, the rule specifies the sequence of segment types (with corresponding actions) to be created when a segment type satisfying the appropriate condition specifications is encountered.

Both encoding and decoding rules have the ability to perform record-to-record information conversion, as previously stated. One modular set of encoding rules known as the MASSAGER [7] is utilized in this way to set default values in the IPD. Certain assumptions about the problem may be made by the user during the discourse. For example, if the number of units of storage capacity required by a mobile entity has not been mentioned, it is probable that an assumption of one unit has been made by the user. The purpose of the MASSAGER is to inspect the IPD after decoding is completed and set default values in those instances where non-controversial assumptions can be made. Other functions include the consolidation of redundant information and the deletion of certain attributes required only for decoding purposes.

Another encoding rule module known as the INTERROGATOR [8] serves to inspect the IPD for missing or erroneous information. Copies of the action records maintained in the IPD are accessed through the 'ACTNLIST' and tested to ensure that they have all of the attributes required for processing by the GPSS/X-VECTOR rule module. When incorrect or missing information is detected, the INTERROGATOR sets up the segment form of the question to be asked and invokes the ENGLISH encoding module to actually produce the question. Information provided by the user is then decoded and the inspection of the IPD continues. The INTERROGATOR may also be utilized to enter the problem in a question-answer fashion. When the necessary information pertaining to the problem has been established, a message is encoded indicating completion of the problem statement.

At any point during the discourse the user may request a statement of the problem as the system "sees" it. The English encoding module [6] provides the conversion necessary to produce an English description of the problem from the information contained in the IPD. The generality of this module also permits the handling of statements to the user generated by other modules such as the INTERROGATOR.

The GPSS/X-VECTOR encoding module [10] is utilized to create a GPSS program and initialize the data structure used by the simulation routine. This data structure, called the X-vector, contains the information necessary to perform the simulation. In addition, it is used throughout the simulation to maintain the required statistics in much the same manner as the internal tables of GPSS [11]

Once the problem has been completely specified, the user may request that a GPSS program be written for the current problem. The semological rules of this module examine the IPD and produce segments which roughly correspond to the statements of a GPSS program. Rules in the lexology further process these segments and their constituents into other segments in the appropriate order for a GPSS program. The morphological rules then produce the corresponding GPSS output.

Similar rules in the X-vector lexology and morphology place pertinent information into the X-vector. Figure 1 (taken from ref. 10) shows an initial X-vector produced by these rules. With the information in the X-vector the simulation can be performed.

## E. THE SIMULATION ROUTINE

This FORTRAN routine, originated by Williams [9], performs a GPSS-like simulation based on the information contained in the X-vector. The initial portion of the X-vector contains "parameters" for the simulation routine. These parameters are assigned fixed locations in the vector. They consist of variables such as the random number seeds to be used, pointers to the various directories, entity allocation counts, clock time, etc. The latter portion of the vector contains allocated space for the various GPSS entities (i.e., STORAGES, QUEUES, TABLES, FUNCTIONS, VARIABLES, SAVEVALUES, and BLOCKS). The directories associated with these entities are also allocated space in this section of the vector. The location of these allocated




Figure 1: Internal Structure of the X-Vector

areas is flexible and is determined by the requirements of the specific problem.

The procedure used to execute the simulation is essentially the same as that of GPSS. Raw results of the simulation, such as the cumulative time integrals for storages and queues, are stored in the X-vector elements associated with these entities. Several simulation modes comparable to the GPSS control cards SIMULATE/START, RESET, CLEAR, and START perform similar functions in the simulation routine.

## III. A SAMPLE SIMULATION PROBLEM

This chapter is intended to demonstrate the capabilities of this initial version of the interactive simulation system being developed. It illustrates how a user may input a queuing problem in English, have the system question him for needed information, obtain a restatement of the problem from the computer, and have the system perform the simulation and output the requested results.

The sample given here is taken from an actual terminal session. In line with the purpose of demonstrating the system's capabilities, a wide variety of statements and questions are given. This results in an unusual amount of redundancy.

Throughout this chapter, all inputs by the user are shown in lower case, and all computer responses are shown in UPPER CASE. This is the way a sample session under CP/CMS would actually appear. Comments are interspersed where needed and are enclosed in parentheses. The sample session begins with "decode:" below.

decode:

(This is a command to NLP necessary to invoke the decoding rules for processing the input text.)

vehicles arrive at a station.

the station has just one pump.

a vehicle will leave the station immediately after

arriving if the length of the line at the pump

is not less than two.

otherwise, it is serviced there; then it leaves.

service times are exponential, with a mean of 5

minutes for cars and 9 minutes for trucks.

three quarters of the vehicles are cars and one

fourth of them are trucks.

is the statement of the problem complete?

(This question results in inspection of the IPD for missing or erroneous information.)

HOW OFTEN DO THE VEHICLES ARRIVE AT THE STATION?

(The question-answer mode is initiated to query the user for necessary information.)

arrivals are normally distributed with a mean of 8

minutes and a standard deviation of 2 minutes.

HOW LONG SHALL THE SIMULATION BE RUN?

the basic time unit to be used in the model is

30 seconds.

(Even though this response does not answer the question, this information is still accepted into the IPD. The system will query the user again for the answer to its question.)

HOW LONG SHALL THE SIMULATION BE RUN?

eight hours.

THE PROBLEM STATEMENT IS COMPLETE.

describe the problem in english.

(This is requesting a restatement of the problem as it now appears in the IPD.)

THE VEHICLES ARRIVE AT THE STATION. THE TIME BETWEEN ARRIVALS OF THE VEHICLES AT THE STATION IS NORMALLY DISTRIBUTED, WITH A MEAN OF 8 MINUTES AND A STANDARD DEVIATION OF 2 MINUTES. 75 PERCENT OF THE VEHICLES ARE CARS, AND THE REST ARE TRUCKS. AFTER ARRIVING AT THE STATION, IF THE LENGTH OF THE LINE AT THE PUMP IN THE STATION IS LESS THAN 2, THE VEHICLES WILL BE SERVICED AT THE PUMP IN THE STATION. OTHERWISE, THE VEHICLES WILL LEAVE THE STATION. THE TIME FOR THE VEHICLES TO BE SERVICED AT THE PUMP IN THE STATION IS EXPONENTIALLY DISTRIBUTED, WITH A MEAN OF 5 MINUTES FOR THE CARS, AND 9 MINUTES FOR THE TRUCKS. AFTER BEING SERVICED AT THE PUMP IN THE STATION, THE VEHICLES LEAVE THE STATION.

THE SIMULATION IS TO BE RUN FOR 8 HOURS, USING A BASIC TIME UNIT OF 30 SECONDS.

write a gpss program for this problem.

(Production of the GPSS program also results in X-vector initialization in preparation for running the simulation. The program produced is shown on the following page.)

```
       SIMULATE
       RMULT        277,423,715,121,655,531,999,813
 STAT1 EQU          1,F,Q
 PUMP2 EQU          2,F,Q
 CAR2  EQU          2,T
 2     TABLE        M1,1,1,2
 TRUC3 EQU          3,T
 3     TABLE        M1,1,1,2
 1     FUNCTION     RN1,C24
0.0,0.0/0.100,0.104/0.200,0.222/0.300,0.355/
0.400,0.509/0.500,0.690/0.600,0.915/0.700,1.200/
0.750,1.390/0.800,1.600/0.840,1.830/0.880,2.120/
0.900,2.300/0.920,2.520/0.940,2.810/0.950,2.990/
0.960,3.200/0.970,3.500/0.980,3.900/0.990,4.600/
0.995,5.300/0.998,6.200/0.999,7.000/1.000,8.000/
 2     FUNCTION     RN2,C29
0.0,-3.000/0.012,-2.250/0.027,-1.930/0.043,-1.720/
0.062,-1.540/0.084,-1.380/0.104,-1.260/0.131,-1.120/
0.159,-1.000/0.187,-0.890/0.230,-0.740/0.267,-0.620/
0.334,-0.430/0.432,-0.170/0.500,0.0/0.568,0.170/
0.666,0.430/0.732,0.620/0.770,0.740/0.813,0.890/
0.841,1.000/0.869,1.120/0.896,1.260/0.916,1.380/
0.938,1.540/0.957,1.720/0.973,1.930/0.988,2.250/
1.000,3.000/
 3     FUNCTION     P1,D2
CAR2,10/TRUC3,18/
 4     FUNCTION     RN3,D2
0.750,CAR2/1.000,TRUC3/
 1     FVARIABLE    16+4*FN2
*
*      THE VEHICLES ARRIVE AT THE STATION.
       GENERATE     V1
       ASSIGN       1,FN4
       TEST L       Q$PUMP2,2,ACT2
       TRANSFER     ,ACT3
*
*      THE VEHICLES LEAVE THE STATION.
 ACT2  TABULATE     P1
       TERMINATE
*
*      THE VEHICLES ARE SERVICED AT THE PUMP.
 ACT3  QUEUE        PUMP2
       SEIZE        PUMP2
       DEPART       PUMP2
       ADVANCE      FN3,FN1
       RELEASE      PUMP2
       TRANSFER     ,ACT2
*
*      TIMING LOOP
       GENERATE     960
       TERMINATE    1
       START        1
       END
```

perform the simulation.

SIMULATION TIME IS 960(RELATIVE), 960(ABSOLUTE).

(This message signals completion of the simulation. The user may now ask for statistical printouts or for specific information concerning the outcome.)

print the gpss statistics.

| STORAGE | CAPACITY | AVERAGE CONTENTS | AVERAGE UTILIZATION | ENTRIES | AVERAGE TIME/TRAN | CURRENT CONTENTS | MAXIMUM CONTENTS |
|---|---|---|---|---|---|---|---|
| 1 | 1 | 0.0 | 0.0 | 0 | 0.0 | 0 | 0 |
| 2 | 1 | 0.659 | 0.659 | 59 | 10.729 | 0 | 1 |

| QUEUE | MAXIMUM CONTENTS | AVERAGE CONTENTS | TOTAL ENTRIES | ZERO ENTRIES | PERCENT ZEROS | AVERAGE TIME/TRANS | $AVERAGE TIME/TRANS | CURRENT CONTENTS |
|---|---|---|---|---|---|---|---|---|
| 1 | 0 | 0.0 | 0 | 0 | 0.0 | 0.0 | 0.0 | 0 |
| 2 | 2 | 0.278 | 59 | 38 | 64.407 | 4.525 | 12.714 | 0 |

$AVERAGE TIME/TRANS = AVERAGE TIME/TRANS EXCLUDING ZERO ENTRIES

TABLE 2

| ENTRIES IN TABLE | MEAN ARGUMENT | STANDARD DEVIATION | SUM OF ARGUMENTS |
|---|---|---|---|
| 43 | 13.628 | 13.175 | 586.000 |

| UPPER LIMIT | OBSERVED FREQUENCY | PER CENT OF TOTAL | CUMULATIVE PERCENTAGE | CUMULATIVE REMAINDER | MULTIPLE OF MEAN | DEVIATION FROM MEAN |
|---|---|---|---|---|---|---|
| 1 | 3 | 6.98 | 6.98 | 93.02 | 0.073 | -0.958 |
| OVERFLOW | 40 | 93.02 | 100.00 | 0.00 | | |

AVERAGE VALUE OF OVERFLOW 14.650

TABLE 3

| ENTRIES IN TABLE | MEAN ARGUMENT | STANDARD DEVIATION | SUM OF ARGUMENTS |
|---|---|---|---|
| 18 | 17.444 | 12.641 | 314.000 |

| UPPER LIMIT | OBSERVED FREQUENCY | PER CENT OF TOTAL | CUMULATIVE PERCENTAGE | CUMULATIVE REMAINDER | MULTIPLE OF MEAN | DEVIATION FROM MEAN |
|---|---|---|---|---|---|---|
| 1 | 2 | 11.11 | 11.11 | 88.89 | 0.057 | -1.301 |
| OVERFLOW | 16 | 88.89 | 100.00 | 0.00 | | |

AVERAGE VALUE OF OVERFLOW 19.625

CURRENT EVENTS CHAIN

| TRANS | BDT | BLOCK | NBA | MARK-TIME | P1 | P2 | P3 | P4 | SI | TI |
|---|---|---|---|---|---|---|---|---|---|---|

FUTURE EVENTS CHAIN

| TRANS | BDT | BLOCK | NBA | MARK-TIME | P1 | P2 | P3 | P4 | SI | TI |
|---|---|---|---|---|---|---|---|---|---|---|
| 3 | 964 | 1 | 2 | 964 | 0 | 0 | 0 | 23658912 | T | T |
| 2 | 1920 | 13 | 14 | 1920 | 0 | 0 | 0 | 372 | T | T |

print the storage statistics.

| STORAGE | CAPACITY | AVERAGE CONTENTS | AVERAGE UTILIZATION | ENTRIES | AVERAGE TIME/TRAN | CURRENT CONTENTS | MAXIMUM CONTENTS |
|---|---|---|---|---|---|---|---|
| 1 | 1 | 0.0 | 0.0 | 0 | 0.0 | 0 | 0 |
| 2 | 1 | 0.659 | 0.659 | 59 | 10.729 | 0 | 1 |

print the pump statistics.

| STORAGE | CAPACITY | AVERAGE CONTENTS | AVERAGE UTILIZATION | ENTRIES | AVERAGE TIME/TRAN | CURRENT CONTENTS | MAXIMUM CONTENTS |
|---|---|---|---|---|---|---|---|
| 2 | 1 | 0.659 | 0.659 | 59 | 10.729 | 0 | 1 |

| QUEUE | MAXIMUM CONTENTS | AVERAGE CONTENTS | TOTAL ENTRIES | ZERO ENTRIES | PERCENT ZEROS | AVERAGE TIME/TRANS | $AVERAGE TIME/TRANS | CURRENT CONTENTS |
|---|---|---|---|---|---|---|---|---|
| 2 | 2 | 0.278 | 59 | 38 | 64.407 | 4.525 | 12.714 | 0 |

$AVERAGE TIME/TRANS = AVERAGE TIME/TRANS EXCLUDING ZERO ENTRIES

print the pump queue statistics.

| QUEUE | MAXIMUM CONTENTS | AVERAGE CONTENTS | TOTAL ENTRIES | ZERO ENTRIES | PERCENT ZEROS | AVERAGE TIME/TRANS | $AVERAGE TIME/TRANS | CURRENT CONTENTS |
|---|---|---|---|---|---|---|---|---|
| 2 | 2 | 0.278 | 59 | 38 | 64.407 | 4.525 | 12.714 | 0 |

$AVERAGE TIME/TRANS = AVERAGE TIME/TRANS EXCLUDING ZERO ENTRIES

print the truck statistics.

TABLE 3

| ENTRIES IN TABLE | MEAN ARGUMENT | STANDARD DEVIATION | SUM OF ARGUMENTS |
|---|---|---|---|
| 18 | 17.444 | 12.641 | 314.000 |

| UPPER LIMIT | OBSERVED FREQUENCY | PER CENT OF TOTAL | CUMULATIVE PERCENTAGE | CUMULATIVE REMAINDER | MULTIPLE OF MEAN | DEVIATION FROM MEAN |
|---|---|---|---|---|---|---|
| 1 | 2 | 11.11 | 11.11 | 88.89 | 0.057 | -1.301 |
| OVERFLOW | 16 | 88.89 | 100.00 | 0.00 | | |

AVERAGE VALUE OF OVERFLOW 19.625

print the car table statistics.

TABLE 2

| ENTRIES IN TABLE | MEAN ARGUMENT | STANDARD DEVIATION | SUM OF ARGUMENTS |
|---|---|---|---|
| 43 | 13.628 | 13.175 | 586.000 |

| UPPER LIMIT | OBSERVED FREQUENCY | PER CENT OF TOTAL | CUMULATIVE PERCENTAGE | CUMULATIVE REMAINDER | MULTIPLE OF MEAN | DEVIATION FROM MEAN |
|---|---|---|---|---|---|---|
| 1 | 3 | 6.98 | 6.98 | 93.02 | 0.073 | -0.958 |
| OVERFLOW | 40 | 93.02 | 100.00 | 0.00 | | |

AVERAGE VALUE OF OVERFLOW 14.650

what is the current contents of the pump?

THE CURRENT CONTENTS OF THE PUMP IN THE STATION IS 0.

what is the s of the pump?

THE CURRENT CONTENTS OF THE PUMP IN THE STATION IS 0.

(Note that the above questions to the system are equivalent. Questions can be asked by specifying the GPSS standard numerical attribute ("s") or by specifying that attribute in English ("current contents").)

what is the sm of the pump?

THE MAXIMUM CONTENTS OF THE PUMP IN THE STATION IS 1.

what is the sa of the pump?

THE AVERAGE CONTENTS OF THE PUMP IN THE STATION IS 0.659.

what is the st at the pump?

THE AVERAGE SERVICE TIME AT THE PUMP IN THE STATION IS 10.729.

what is the qz at the pump?

THE NUMBER OF ZERO ENTRIES AT THE PUMP IN THE STATION IS 38.

what is the qx at the pump?

THE AVERAGE WAITING TIME EXCLUDING ZERO ENTRIES AT THE PUMP IN THE STATION IS 12.714.

what is the maximum line at the pump?

THE MAXIMUM LINE LENGTH AT THE PUMP IN THE STATION IS 2.

what is the current line at the pump?

THE CURRENT LINE LENGTH AT THE PUMP IN THE STATION IS 0.

what is the mean transit time of the cars?

THE MEAN TRANSIT TIME OF THE CARS IS 13.627.

what is the average line at the pump?

THE AVERAGE LINE LENGTH AT THE PUMP IN THE STATION IS 0.278.

what is the average utilization of the pump?

THE AVERAGE UTILIZATION OF THE PUMP IN THE STATION IS 0.659.

what is the average waiting time at the pump?

THE AVERAGE WAITING TIME AT THE PUMP IN THE STATION IS 4.525.

what is the average time at the pump?

THE AVERAGE SERVICE TIME AT THE PUMP IN THE STATION IS 10.729.

continue the simulation.

(This is comparable to the encountering of a second or subsequent "start" card in GPSS. The simulation progresses from the point at which it previously terminated.)

SIMULATION TIME IS 1920(RELATIVE), 1920(ABSOLUTE).

what is the average utilization of the pump?

THE AVERAGE UTILIZATION OF THE PUMP IN THE STATION IS 0.654.

what is the average waiting time at the pump?

THE AVERAGE WAITING TIME AT THE PUMP IN THE STATION IS 6.111.

what is the average time at the pump?

THE AVERAGE SERVICE TIME AT THE PUMP IN THE STATION IS 10.930.

(The three questions above were asked in order to show the effect the longer simulation time had on the previous results.)

continue the simulation

SIMULATION TIME IS 2880(RELATIVE), 2880(ABSOLUTE).

what is the average utilization of the pump?

THE AVERAGE UTILIZATION OF THE PUMP IN THE STATION IS 0.701.

what is the average waiting time at the pump?

THE AVERAGE WAITING TIME AT THE PUMP IN THE STATION IS 8.674.

what is the average time at the pump?

THE AVERAGE SERVICE TIME AT THE PUMP IN THE STATION IS 12.242.

reset and start the simulation.

(This is similar to using the control cards "reset/start" in GPSS.)

SIMULATION TIME IS 960(RELATIVE), 2840(ABSOLUTE).

what is the average utilization of the pump?

THE AVERAGE UTILIZATION OF THE PUMP IN THE STATION IS 0.768.

what is the average waiting time at the pump?

THE AVERAGE WAITING TIME AT THE PUMP IN THE STATION IS 9.732.

what is the average time at the pump?

THE AVERAGE SERVICE TIME AT THE PUMP IN THE STATION IS 12.982.

clear and restart the simulation.

(This is similar to using the control cards "clear/start" in GPSS.)

SIMULATION TIME IS 960(RELATIVE), 960(ABSOLUTE).

what is the average utilization of the pump?

THE AVERAGE UTILIZATION OF THE PUMP IN THE STATION IS 0.732.

what is the average waiting time at the pump?

THE AVERAGE WAITING TIME AT THE PUMP IN THE STATION IS 14.132.

what is the average time at the pump?

THE AVERAGE SERVICE TIME AT THE PUMP IN THE STATION IS 13.557.

are there two pumps in the station?

(This question results in an inspection of the IPD to determine the number of pumps.)

NO, THERE IS 1 PUMP IN THE STATION.

the station should have two pumps.

(This statement results in an updating of the IPD to reflect this new information.)

how often does a vehicle arrive?

THE TIME BETWEEN ARRIVALS OF THE VEHICLES AT THE STATION IS NORMALLY DISTRIBUTED WITH A MEAN OF 8 MINUTES AND A STANDARD DEVIATION OF 2 MINUTES.

the mean of the time between arrivals should be 3 minutes,

and the deviation of the time between arrivals should be 1

minute.

develop the x vector.

(Since the IPD has been altered, the X-vector must be reinitialized prior to simulation to reflect the changes made. In this case a GPSS program printout is not desired.)

perform the simulation.

(This results in the simulation being performed with the X-vector for the modified problem.)

SIMULATION TIME IS 960(RELATIVE), 960(ABSOLUTE).

what is the average utilization of the pumps?

THE AVERAGE UTILIZATION OF THE PUMPS IN THE STATION IS 0.093.

what is the average waiting time at the pumps?

THE AVERAGE WAITING TIME AT THE PUMPS IN THE STATION IS 3.882.

what is the average time at the pumps?

THE AVERAGE SERVICE TIME AT THE PUMPS IN THE STATION IS 10.529.

# IV. IMPLEMENTATION

Achieving the objectives of this research required making additions and changes to the FORTRAN routines of NLPQ and to the rules and declarations processed by those routines. This chapter, which is intended to explain the modifications, has been divided into two sections. The first section describes the FORTRAN modifications, and the second section describes the rule modifications.

## A. FORTRAN ROUTINES AND MODIFICATIONS

The main FORTRAN programming effort involved major alterations and additions to the simulation routine. A few additional modifications to NLP were needed, however, in subroutines PRINT, ENCODE, and CRSEG. A discussion on each of these four areas follows.

### 1. NLP Modifications to Allow X-Vector Read and Write

This section was added simply for the convenience of the user. It gives the user a method for saving the contents of the X-vector as a binary file for use in a later terminal session. By doing this the user does not have to duplicate his efforts from a previous session to arrive at the same point in a given simulation. He need only initialize the current X-vector with the contents of the previous X-vector.

The FORTRAN routine for performing this function is shown in Appendix A. This routine was added as entry point XRDWR

("X-vector Read/Write") in subroutine PRINT. The routine may be invoked at any time as a command to NLPQ. The format for a call to XRDWR from the terminal is

$$X_{\wedge}READ_{\wedge}f: \quad \text{or} \quad X_{\wedge}WRITE_{\wedge}f: \quad ,$$

where "f" is an integer number of any available file under CP/CMS and "$_{\wedge}$" denotes at least one blank space. As an example, the command "X WRITE 3:" would cause the current contents of the X-vector to be written into file FT03F001 as a binary file.

2. Establishing a Linkage for Communication

The rule language of NLP utilizes declared ROUTINES to communicate with the various FORTRAN subroutines. The appearance of a routine name in a rule causes execution of the code for that particular routine in subroutine CRSEG ("Create Segment"). To establish communication between the rules and the simulation subroutine, therefore, it was necessary to add an additional routine in subroutine CRSEG to communicate with each entry point in the simulation subroutine. The FORTRAN code for establishing this communication is given in Appendix A.

The four entries into the simulation subroutine (SIMULT, SIMOUT, SETIND, and SPSTAT) will be discussed in detail later in this section. At this point it is sufficient to say that SIMULT ("Simulation") and SIMOUT ("Simulation Output") require no information from the rule segment being processed. In addition, they are

called merely to perform their functions and not to return a value. Hence, execution of these routines in CRSEG simply results in a call to the appropriate entry point in the simulation subroutine.

Both SETIND ("Set Indicators") and SPSTAT ("Specific Statistics"), however, require the value of certain attributes of the segment being processed to be passed as arguments. In addition, SPSTAT returns a value which must be made available to the segment being processed. The additional coding in CRSEG for these two routines sets up this communication.

3. Modified Output Routine

The output routine in subroutine ENCODE was originally implemented to handle only integer half-word values (or integer half-word values expressed in parts per thousand) and, therefore, could output only integers in the range -32768 to 32767 or real values in the range -32.768 to 32.767. This was acceptable when the only output from the system was a GPSS program. With the incorporation of the simulation routine and the ability to actually run the simulation at the terminal and question the system for such items as the mean transit time or the average utilization, however, this limitation became unacceptable. As a result, the output routine was rewritten to handle the magnitude of any integer or real value which could be stored in a full-word on the IBM 360. The modified section of ENCODE pertaining to the output of numerical values is shown in Appendix A.

To output a numerical value from an OUTPUT segment, the segment must have an attribute (ATTR or @) 14, 15, or 16. An integer or real value will then be output in accordance with one of the four cases described below.

Case 1. If an @14 cell is present and the TYPE of the cell is "0", then the value in the address (ADDR) field is taken to be a half-word integer.

Case 2. If an @14 cell is present and the TYPE of the cell is "1", then the value of the ADDR field is taken to be a pointer to another cell whose value is a full-word found in the ADDR and LINK fields. This value is taken to be an integer unless a "1" is present in the ATTR field of the same cell, in which case the number is considered to be floating point.

Case 3. If an @15 cell is present, then the value in the ADDR field is taken to be a real number expressed as a half-word integer in parts per thousand.

Case 4. If an @16 cell is present, then the value in the ADDR field is taken to be a pointer to another cell whose value is a full-word found in the ADDR and LINK fields. This number is evaluated as in Case 2 above.

These four methods of handling numerical values in an OUTPUT segment are illustrated in Figure 2.




Figure 2: Numerical Evaluation for OUTPUT Segment.

4. <u>The Simulation Subroutine</u>

As previously mentioned, modifications to the simulation subroutine (called SIMULT) constituted the major FORTRAN programming effort involved in the preparation of this thesis. A complete listing of the subroutine is given in Appendix C. This listing is preceded by an extensive dictionary of variables (Appendix B) to assist the reader in understanding the logic of the program. Even though SIMULT is only a subroutine of NLPQ it is quite extensive and requires a considerable amount of core. The source deck contains approximately 1600 cards, and a region of 250K is needed for compilation under OS/360. A slightly larger region is required under CP/CMS. Approximately one and one-half minutes of CPU time are required for compilation using the FORTRAN G-level compiler, and the resultant object module occupies approximately 40K bytes in the IBM 360. The subroutine contains four entry points. It can be accessed by calls to SIMULT, SIMOUT, SETIND, or SPSTAT. Each of these sections will be discussed individually at this point.

a. SIMULT

This is the main entry into the simulation subroutine. A call to SIMULT is a request to perform the simulation based on the information found in the X-vector. For this reason the user must ensure that the vector has been properly initialized prior to requesting that a simulation be performed. If the user desires to continue the problem from a previous session in which the contents of the

vector were saved, he may utilize the X READ feature described previously to initialize the current X-vector. If this is not the case, however, the user must either tell the system to develop an X-vector, or he must tell the system to write a GPSS program, in a manner to be described later. The former case will result in only the initialization of the X-vector based on the information contained in the IPD. No output will be sent to the terminal. The latter case will result in both the GPSS program being output and the concurrent initialization of the X-vector. It is important to note that even though NLP gives the user the capability of saving the internal problem description and reinitializing the system with that IPD at a later date, this procedure does not reinitialize the X-vector.

The SIMULT section is basically the simulation routine written by R. J. Williams [9]. The basic logic flow and the structure of the various statistical entity layouts described by Williams were retained in the implementation of the simulation capability to NLPQ. The reader interested in following the logical flow of the SIMULT listing is advised, therefore, to reference Williams' work for the physical layout of the various statistical entities (STORAGE, QUEUE, TABLE, etc.).

Major alterations to the basic flow of transactions through the system were made upon incorporation of the simulation routine into NLPQ. For example, a reordering of the sequences involved for merging transactions of equal priority into their

appropriate positions on the current and future events chains was needed in the verification phase to ensure that transactions would be executed in the same sequence as is done in GPSS. Modifications were also required in the procedures associated with determining when a status change has occurred within the system. These modifications further altered the original flow of transactions since these procedures determine at what points in the simulation a scan of the current events chain should be continued from its previous position and at what points it should be restarted from the beginning of the chain.

Additional modifications included the addition of the entire section pertaining to the updating of the system performed during the final time interval prior to terminating the simulation. This area had been completely omitted in Williams' work but was needed to ensure agreement between the statistical outputs of GPSS and subroutine SIMULT. This section primarily performs an update of the STORAGE and QUEUE statistics to reflect the effect of the simulation time involved between the time the storage or queue last changed status and the time the simulation was actually terminated. The ability to output a selected portion of the X-vector was also included in this section.

Further modification to the original simulation subroutine involved the addition of code throughout the routine to avoid system interrupts, such as divide checks, when working with empty

storages, queues, and tables. Similar modifications were also required throughout the routine to ensure that null pointers in the various directories were recognized as such and not used as valid indices when storing or retrieving information pertaining to the subscripted X-vector.

The ability to properly handle clear, reset, and continue commands by the user required some alterations to properly re-initialize the allocated storages, queues, and tables. In addition the procedure for processing the TERMINATE block was modified to ensure replacement of the timing loop generate block on the future events chain. The use of both an absolute and relative clock during the simulation was deleted and replaced by a single clock (absolute) for use during the simulation. A base clock is set in the RESET area to allow computation of the relative time in the two instances in which a relative time is required, i.e., (1) the "C1" Standard Numerical Attribute and (2) the message signaling completion of the simulation.

The section for argument evaluation was altered and expanded somewhat to allow requests for specific statistics (entering the routine via SPSTAT) to access that area of code for evaluation of the statistical information requested. Most of the remaining alterations to the original routine were either minor in nature or made simply in the interest of cleaner coding.

SIMULT is entered upon a user request to perform the simulation or a request to clear, reset, or continue the simulation. Initialization of the simulation model is then performed, if necessary, based on the type of request made. This initialization is analogous to that performed by GPSS upon encountering the control cards SIMULATE/START, CLEAR, RESET, and START. The algorithms which direct the flow of transactions through the system from this point are essentially the same algorithms used in GPSS. Since the results produced by the program, as well as the information needed to perform the simulation, are contained in the X-vector, execution of SIMULT results in an X-vector altered to reflect the current status of the simulation. The results, therefore, are readily available to be accessed in the event the user requests information concerning the outcome of the simulation. Assuming no error conditions are encountered during the simulation, the only output from a SIMULT entry will be a message giving the absolute and relative simulation clock times. This message signals completion of the simulation.

b. SIMOUT

The "Simulation Output" routine is invoked whenever the user requests GPSS-like statistical information. The format of the information output by SIMOUT is practically identical to that of GPSS. Unlike GPSS, however, SIMOUT has the capability of providing the user with (1) an entire statistical printout (including storage and queue statistics, tables, savevalues, the current events chain, and the future

events chain), (2) a single block of any of the statistics just mentioned (the storage statistics alone, for example), (3) a single line of storage or queue statistics for a single table of several tables (for example, the queue statistics for a specified stationary entity), or (4) the queue and storage statistics for any specified stationary entity (such as a pump). For example, a user request to "print the GPSS statistics" will result in (1) above. Similarly, "print the storage statistics" will result in (2) and "print the pump queue statistics" will result in (3). If the user's request is "print the pump statistics", the SIMOUT routine will output both the storage and queue statistics for the pump. This will be explained more fully later.

The SIMOUT routine has no access to the current segment being processed. Yet the routine needs to know exactly which lines are to be output and which are not. This information is obtained from a vector called STATSW ("Statistic Switches"). This vector is local to the SIMULT routine and, hence, can be accessed by both SIMOUT and SETIND. It is the function of SETIND (which will be described later in this section) to set the proper statistic switches for SIMOUT. A call to SIMOUT, therefore, must always be preceded by a call to SETIND. These calls, however, result from the processing of the input text and are made from subroutine CRSEG. They are completely transparent to the user.

STATSW (shown in figure 3) is a four element, real*8 vector. The first three elements contain indicators for storages, queues, and tables, respectively. The rightmost 55 bits in each




Figure 3: Statistic Switch Vector.

element are used to indicate which storage, queue, or table should be output. If the first element in STATSW has a "1" in bit position two and zeros elsewhere, for example, the SIMOUT routine would output the storage statistics for the stationary entity which has an identification number (IDNO) of two in the IPD. The storage statistics for the remaining stationary entities would not be printed. Indicators for queues and tables are treated similarly, with the exception that the IDNO for the table refers to a mobile entity in the IPD.

The fourth element in STATSW contains indicators for savevalues and the current and future event chains. Only the rightmost three bits are used. A "1" in the third bit position of element four, for example, would indicate the future events chain is to be output. The bit pattern shown in figure 3 indicates that storage and queue statistics for the stationary entity having an IDNO equal to 3 is to be output. No other statistics are to be printed.

Upon entry into SIMOUT a call is immediately made to subroutine GBITS ("Get Bits"). This routine returns the value of bits 1 through 55 of the first STATSW element. A zero value indicates no storage statistics are to be output. In this case a branch is made around the "output storage" area to the "output queue" area. If the value returned is not zero, however, then one or more lines of storage statistics are to be output. SIMOUT, therefore, outputs the storage headings and then begins a search to determine which of the storages are to be output. This is done by successive calls to GBITS to obtain

the value of bit positions 1, 2, 3, ...(up to the number of storages being maintained in the system). If the individual bit value is "0", that storage is bypassed. If the bit value is "1", however, SIMOUT utilizes the current information in the X-vector for that particular storage to calculate and output the statistics required. When this has been done for each storage, the program falls through to the "output queue" area.

The procedure for determining which queues and tables are to be output, if any, is the same as that for storages. Upon falling through to the "output savevalues" area, however, only one call to GBITS is made to determine if bit position one of STATSW(4) is on. If this is the case, all of the savevalues are listed with their respective values.

The procedure for determining whether the current and future events chains (bit positions two and three) are to be output is essentially the same as that for savevalues. The noticeable difference in output of the chains is that both are handled in the same area in order to avoid duplication of code.

Upon completion of the statistical outputs, SIMOUT zeros all four elements of STATSW prior to returning to CRSEG. This is required to prevent unwanted statistics from being printed if the user later requests further information requiring another call to SIMOUT.

c. SETIND

As mentioned previously, it is the function of SETIND ("Set Indicators") to set the desired bits in the STATSW vector to enable SIMOUT to output the proper statistics. It is a function of the decoding rules to determine the content of the English request and issue a call to SETIND, telling the routine which bits are to be set. Like all calls to the simulation routine, this call is made via subroutine CRSEG.

SETIND must receive two parameters from the calling segment. These parameters are (1) the row in STATSW which is affected and (2) the bit position (or positions) within that row which is to be set. Since a single request for statistics by the user may involve the setting of a single row or multiple rows and may involve the setting of a single bit or all the bits within a given row, this capability has been included in SETIND in order that these multiple settings might be performed by a single call to SETIND. This is accomplished by the manner in which SETIND handles the calling arguments. If the requested row is in the range 1 through 4, the routine assumes the row specified is to be set. If the calling argument for the row is 5, however, the routine assumes that the bit (or bits) specified are to be set in both rows 1 and 2 of STATSW. This condition is common to a request for statistics of stationary entities (which have both storage and queue statistics). A calling argument of 6 specifies that all the bits of each element are to be set. This corresponds to a total

GPSS-like printout. If the second calling argument (the bit position to be set) is in the range 1 through 55, that single bit position is set. If the second argument is greater than 55, however, then all of the bits of the specified row are turned on. This condition is common when issuing a request for statistics without specifying an associated stationary or mobile entity.

The actual setting of the bit positions is not necessarily performed by SETIND. SETIND merely analyzes the request to determine which bits are to be set. If an entire row in STATSW is to be turned on, SETIND will perform the function. If only a single bit is to be turned on, however, SETIND issues a call to subroutine PBITS ("Put Bits") to set the desired bit position. Once the desired bits have been set, SETIND returns to the calling routine, CRSEG.

d. SPSTAT

A user request for a single item of statistical information is processed by the rules in a manner similar to any other question to the system. The value of most items of statistical interest, however, is not available in the IPD. When it is determined in the processing of the text that one of these values is being requested, attributes are set in the segment being processed to designate the type of value being requested and the IDNO of the entity for which the value is to be computed. A call is then made through CRSEG to SPSTAT ("Specific Statistics") passing these attributes as parameters.

SPSTAT sets an initial default value of zero to be returned in the event an error condition occurs (such as a request for statistical information prior to performing the simulation). The routine then sets an entry point flag and branches into the SIMULT argument evaluation section to compute the desired statistic. As previously mentioned, this section in SIMULT was modified to be able to process inputs from both entry points. A SIMULT entry into this section causes all real argument values to be truncated to integer values. An SPSTAT entry, however, requires that real values be retained and returned as floating point.

Upon completion of argument evaluation, the entry point flag directs the logical flow back to SPSTAT. The bit pattern of the value is set into an integer word and a flag is set to specify whether the value being returned should be interpreted as an integer or a decimal result. The requested value and the flag are then passed back to CRSEG which inserts the information into the current segment record to be output later in the encoded text.

## B. RULE ADDITIONS AND MODIFICATIONS

Integration of the simulation routine and the ability to query the system as to the results of the simulation required several modifications and additions to the existing rule modules. Expansion of the concept structure by the addition of named record definitions was also necessary to allow questions relating to the simulation results.

The changes and additions made are shown in Appendix D and are discussed in the following sections.

1. Named Records

Several named records in the form of English words with their associated part-of-speech (PS) attributes were added to facilitate recognition of these words by the system. The GPSS entities, storage, queue, and table, were also declared and assigned numerical codes which correspond to the position of their respective indicators in the STATSW vector previously described. A superset relation is also established to identify these words as elements of the set 'GPSSENTY' ("GPSS entity").

The remaining named record definitions identify the various GPSS "Standard Numerical Attributes" (SNA's) as members of the set 'GPSSATTR' ("GPSS attribute"). Each of these records also contains an SNACODE attribute with an associated value. This value is passed to the SPSTAT routine by the rules in those instances where a specific statistic is desired. The CHARS attribute contains the SNA name in character form to be used in encoding responses to the user's questions.

2. Simulation Control Commands

To permit interactive control of the simulation with regard to the various modes of operation, several semological decoding rules were required. These rules are basically "key word" rules which serve to test the input string for the presence of one or more

key words. Rules of this type have a left segment type of KWDSENT. The condition specifications of these rules indicate the key words necessary for rule execution. For example, the presence of the key word "perform", "simulate", or "run", in the user's request results in execution of the simulation routine in the SIMULATE/START mode. Thus the commands; "Perform the simulation.", "Simulate the system.", or just "run.", are equivalent and result in the simulation being run.

The keywords "reset", "clear", and "continue" are handled in a similar manner. Thus by using commands such as "Reset and start the simulation.", "Clear the model.", or "Continue the simulation.", the user can control the mode of the simulation. The key word rules which handle these cases set the mode indicator of the X-vector (X(1)) to the appropriate value and reset the termination count. In the present application, the termination count is set to 1 since the GPSS/X-VECTOR rules use a "timing" transaction to terminate the simulation. The simulation is automatically restarted once these modifications have been made.

Several other functions are also performed by the key word rules. The key words "gpss" or "vector" occurring in the input command result in the initialization of the X-vector from the IPD. If only the key word "vector" is present, for example "Develop the x vector.", the GPSS program will be suppressed. If "gpss" is present, both the GPSS program and the X-vector initialization will

result. The presence of the key words "print" and "gpss" combined with the absence of the key word "program" produce a complete GPSS statistical listing. Thus, "Print the gpss statistics." and similar constructions produce output with the complete results of the simulation. The key words "print", "current", and "events" appearing in the input text result in a printout of the transactions on the current events chain. Omission of, or substitution for, the key word "current" produces a listing of the future events chain. Combination of key words which satisfy more than one rule (e.g., "Reset and run.") will result in execution of the first applicable rule based on their physical order as shown in Appendix D.

### 3. Producing Selective Simulation Results

Several rules were added to NLPQ to give the user the opportunity to request certain portions of the GPSS-like statistical printout. The general format for commands of this type is:

$$\text{PRINT} \quad \left\{\text{THE}\right\} \quad \left[\begin{Bmatrix}\text{stationary entity}\\ \text{mobile entity}\end{Bmatrix} \quad \left\{\text{GPSS entity}\right\}\right] \quad \text{STATISTICS.}$$

Thus commands of the form "Print storage statistics." result in that portion of the statistical printout related to the GPSS entity specified; in this case, the storages. The GPSS entities which can presently be employed are "storage", "queue", and "table". The command "Print pump statistics." satisfies the general format and produces all statistical output related to the stationary entity "pump". In the present application, the statistical output produced for stationary

entities is the appropriate line of storage and queue statistics, with their respective headings. Substitution of a mobile entity in the same form (e.g., "Print truck statistics.") produces table statistics for that mobile entity.

Further selectivity can be obtained by supplying more optional information as in the command "Print the pump queue statistics." In this instance only the line of output associated with the queue at the pump will be printed. The corresponding command for mobile entities (e.g., "Print the truck table statistics.") is equivalent to the earlier mobile entity command and also results in a table. Care must be taken when utilizing this form to ensure that the selection of entities is compatible. Stationary entities must be used in context with the GPSS entity "storage" or "queue". Mobile entities require the use of the GPSS "table" entity. Incorrect sequences may result in alternate statistics or none at all.

The rules for processing these "print commands" are included in the portion of the "Lexology for Decoding English" shown in Appendix D. The processing is based on the appearance of noun phrases which are elements of either the set 'GPSSENTY' or 'ENTITY'. A noun phrase (NOUNPH) which is in the set (denoted by $) 'GPSSENTY', such as "the storage", results in a STATPH segment containing the appropriate code for that entity in attribute eight. Occurrence of the STATPH segment in the context "print STATPH statistics." results in the creation of a PRINTPH segment which

produces the appropriate calls to SETIND and SIMOUT to output the block or line of statistics. The calling parameters used for SETIND are the values of attributes eight and nine of the PRINTPH segment. These attributes and values are copied directly from the STATPH segment.

STATPH segments are also produced by noun phrases in the sets 'STATENTY' ("stationary entity") and 'MOBENTY' ("mobile entity"). These instances, such as "the pump" or "the car" in the proper context result in the production of the single lines of output corresponding to stationary entities or the table statistics for mobile entities. A series of two noun phrases, the first of which is in the set 'ENTITY' (either stationary or mobile) followed by a noun phrase in the set 'GPSSENTY' (storage, queue, or table) also results in the creation of a STATPH. In this case, attribute eight is set to the code of the GPSS entity (accessed via the second noun phrase), and attribute nine is set to the identification number of the entity (via the first noun phrase). These parameters are then used in the SETIND routine to indicate the pertinent line of statistics to be produced by SIMOUT. A comparison of the rules and the general format described earlier provides an insight into the way in which these commands are presently handled.

4. Interrogating the Simulation Results

Additional rules were also incorporated to allow the user to ask questions about specific results of the simulation. With this added

capability, total, partial, or individual statistics are readily available to the user. Presently acceptable questions are of the form:

$$\text{WHAT IS} \left\{\text{THE}\right\} \begin{bmatrix}\text{SNA name}\\ \text{SNA}\end{bmatrix} \begin{bmatrix}\text{OF}\\ \text{AT}\end{bmatrix} \left\{\text{THE}\right\} \begin{bmatrix}\text{Stationary Entity}\\ \text{Mobile Entity}\end{bmatrix} ?$$

The SNA's currently in use are those which correspond with the individual statistical elements produced in the GPSS-like printout. They are listed in the named record definitions in Appendix D (beginning with 'SC'). The character string attribute (CHARS) of each of these records serves as a natural language "SNA name" which can also be used in most instances. In utilizing the question form above, the user again must ensure compatability between the SNA (or SNA name) and the type of entity statistic desired.

The two questions, "What is the SR of the pump?" and "What is the average utilization of the pump?", are equivalent and produce a response with the appropriate number. The same is true of the questions "What is the TB of the trucks?" and "What is the mean transit time of the trucks?". The only SNA's available presently for the mobile entities are TB, TC, and TD, which are "mean transit time", "number of entries", and "standard deviation". Storage and queue individual results may be obtained by using the SNA's SC, SM, SR, SA, S, R, ST, Q, QA, QM, QC, QZ, QT, QX, or QP with their associated stationary entity. The English name of each of these SNA's is contained in the CHARS attribute of the corresponding named record in Appendix D.

The rules for recognizing SNA names are also contained in the decoding lexology. Individual rules exist for each allowable SNA name. For example, in the question, "What is the current line at the pump?", "current line" results in a noun phrase segment in the set 'Q'. This noun phrase segment is later processed by an encoding rule (QUEST2) which tests for this set relation. Satisfaction of the rule conditions result in a sentence segment with attribute eight containing the SNACODE of the desired statistic and attribute nine containing the IDNO of the mobile or stationary entity. Using the values of attributes eight and nine as calling parameters, SPSTAT is called to return the value of the desired statistic. The value returned is then used in the response to the user.

## V. CONCLUSIONS AND RECOMMENDATIONS

The thesis objective has been met. The simulation routine and associated rules have been integrated into the existing NLPQ system to produce an initial version of an interactive simulation system. With this feature, the NLPQ user can perform, and control the mode of, the simulation for his specific problem by using natural language commands. The results of the simulation may be requested in several ways. A complete GPSS-like printout is available or the user may select those portions of the printout which are of interest in his specific problem. Blocks of statistics (storage, queue, table, etc.) or individual lines of the statistical output are readily accessible by the user in the latter instance. Specific statistical results may also be requested in a question-answer fashion. Using these additional features, the user can solve queuing system problems in an interactive manner through natural language dialogue with the system.

Recommendations for further research include expansion of the present question handling abilities to allow further interrogation of the simulation results in a less stringent manner. The ability to detect incompatibilities in input questions and commands and produce meaningful error analyses would enhance the present interaction with the user. Extension of the present features of the simulation routine

to include a larger subset of those functions performed by GPSS, combined with the necessary rule language additions, would provide the user with greater power in solving more complex problems. Further enlargement of the present rule modules to permit interactive ability in specifying table limits, run times, and other GPSS attributes, would enable greater specification and control of the simulation by the user. A means of handling situations in which aggregate statistics are desired (for example, the station statistics should reflect the aggregate statistics for the pump or pumps in the station), would also be of value in improving the usefulness of the system.

APPENDIX A

*** NLP MODIFICATION TO ALLOW ***
X VECTOR READ OR WRITE

```
C                                                                 XRDWR
      ENTRY XRDWR
  501 J=J+1
      IF (COL(J).EQ.BLANK) GO TO 501
      IF (COL(J).EQ.COLON) CALL ERRORA(J,9,&550)
      CALL COLECT(NAME)
  511 J=J+1
      IF (COL(J).EQ.BLANK) GO TO 511
      IF (COL(J).EQ.COLON) CALL ERRORA(J,9,&550)
      CALL CONVRT(NUM)
      IF (NUM.LT.1.OR.NUM.GT.14) CALL ERRORA(J,10,&550)
      NUM4=NUM
      IF (NAME.EQ.XRD) GO TO 531
      IF (NAME.EQ.XWR) GO TO 541
      CALL ERRORA(J,9,&550)
  531 REWIND NUM4
      READ (NUM4) (X(I),I=1,MAXX)
      RETURN
  541 REWIND NUM4
      WRITE (NUM4) (X(I),I=1,MAXX)
  550 RETURN
      END
```

*** ADDITICNAL ROUTINES ***

```
C                                                       SIMULT
 3210 CALL SIMULT(TR6,CUT6,RTERM,WTERM)
      GO TO 1200
C                                                       SIMOUT
 3220 CALL SIMOUT(OUT6)
      GO TO 1200
C                                                       SETIND
 3230 ROW=HVAL(A8,SEGMNT)
      BIT=HVAL(A9,SEGMNT)
      CALL SETIND(ROW,BIT)
      GO TO 1200
C                                                       SPSTAT
 3240 SNA=HVAL(A8,SEGMNT)
      IDT=HVAL(A9,SEGMNT)
      CALL SPSTAT(SNA,IDT,VAL,IORD)
      LX=LOC(A9,SEGMNT)
      CEL=CELL(LX)
      TYPE=1
      ADDR=NEWCEL(CONSTR(ZERO,IORD,PVAL(1),PVAL(2)))
      CELL(LX)=CEL
      GO TO 1200
```

*** MODIFIED OUTPUT ROUTINE ***

```
C                                                         PROCESS 'OUTPUT'
C
  201 N = HVAL(A11,SEGMNT)
      IF (N.GT.0)  CALL OUTCHR(DZERO)
      N = N - 1
      IF (N.GT.0)  CALL SKIP(N)
      KOL = HVAL(A12,SEGMNT)
      IF (KOL.GT.0) CALL SETJJ(KOL)
      NXTWRD = 0
      FWRD = LOC(A13,SEGMNT)
      IF (FWRD.EQ.0) GO TO 231
  221 WORD = DVALUE(FWRD,NXTWRD)
      DO 225 I=8,64,8
         CHR = DOR(DLS(DRS(WORD,64-I),56),DZB)
  225    IF (CHR.NE.DBLANK) CALL OUTCHR(CHR)
      IF (NXTWRD.NE.0) GO TO 221
  231 LOCC = LOC(A14,SEGMNT)
      IF (LOCC.EQ.0) GO TO 241
      DCM=0
      CEL=CELL(LOCC)
      IF (TYPE.EQ.1) GO TO 253
      RN=ADDR
      GO TO 257
  241 LOCC = LOC(A15,SEGMNT)
      IF (LOCC.EQ.0) GO TO 251
      DCM=1
      CEL=CELL(LOCC)
      RN=ADDR/1000.
      GO TO 257
  251 LOCC=LOC(A16,SEGMNT)
      IF (LOCC.EQ.0) GO TO 131
      CEL=CELL(LOCC)
  253 CEL=CELL(ADDR)
      DCM=ATTR
      IF (DCM.EQ.1) GO TO 255
      RN=I4
      GO TO 257
  255 RN=R4
  257 IF (RN.GE.0.) GO TO 261
      RN=-RN
  259 CALL OUTCHR(DMINUS)
  261 IF (RN.GT.1.0E10) GO TO 298
      SW=0
      DO 265 I=1,13
      II=10-I
      IF (DCM.EQ.0.AND.II.EQ.-1) GO TO 131
      M=RN/10.**II+0.0005
      IF (SW.EQ.0.AND.M.EQ.0.AND.II.GT.0) GO TO 265
      SW=1
      IF (DCM.EQ.1.AND.II.EQ.-1) CALL OUTCHR(DECPNT)
      CALL OUTCHR(DIGIT(M+1))
      RN=RN-M*10.**II
  265 CONTINUE
      GO TO 131
  298 WRITE (OUT6,299) RN
  299 FORMAT (' NUMBER EXCEEDS ''OUTPUT'' LIMIT.  VALUE IS '
     1,E13.7)
      CALL OUTCHR(DSTAR)
      CALL OUTCHR(DSTAR)
      CALL OUTCHR(DSTAR)
      GO TO 131
      END
```

## APPENDIX B

## DICTIONARY OF VARIABLES USED

## IN THE SIMULATION ROUTINE

| | |
|---|---|
| ALTBLO | Alternate block number for TEST or GATE routines. |
| AVAIL | Amount of storage available in a given storage entity. |
| BASE | Value to which spread will be added in GENERATE and ADVANCE blocks to determine departure time from the FEC. |
| BITTS | Value of requested bit pattern returned from call to GBITS. |
| BLOCK | Pointer to word preceding block directory in X-vector (BLOCK=X(19)). |
| BYTE (*) | Logical*1 temporary variable (BYTE(1)=DWORD(1)). |
| CBLO | Pointer to current block being processed. |
| CKPNT | Check point used for following traces when debugging. |
| CLOCK | Absolute clock time (CLOCK=X(11)). |
| CLOCKB | Base clock time needed to compute relative clock time after RESET. |
| CLOCKR | Relative clock time. |
| COMVAL | Comparison value used in SELECT blocks. |
| CQUE | Pointer to current queue being processed. |
| CREATE | Time differential between current clock and time transaction is due to leave the FEC. |

| | |
|---|---|
| CSTO | Pointer to current storage being processed. |
| CTRA | Pointer to current transaction being processed. |
| DELAY | Time delay caused by ADVANCE block. |
| DONES | Real*8 mask consisting of all ones. |
| DTIME | Real*8 time differential between clock and time queue or storage last changed status. |
| DW* | See DWORD(*). |
| DWORD(*) | Real*8 temporary variable (DW*=DWORD(*)). |
| EPT | Variable which flags entry point at which SIMULT was entered. |
| ERR | Flag set when an error is encountered (ERR=X(30)). |
| ERRORZ | Subroutine called to output error message and set ERR flag. |
| FB | Variable which specifies which bits to set when calling SETIND or the first bit to set when calling PBITS. |
| FFW* | See FFWORD(*). |
| FFWORD(*) | Real*4 temporary variable (FFW*=FFWORD(*); FFWORD(1)=DWORD(1)). |
| FLAG | Temporary variable used as a logical flag when needed. |
| FOS(*) | Stack for evaluating floating point arguments (FOS(*)=OS(*)). |
| FREWDT | Width of frequency interval in a table entity. |
| FRNG | Number of frequency intervals in a table entity. |
| FTCEC | Pointer to the first transaction on the Current Events Chain (FTCEC=X(26)). |

| | |
|---|---|
| FTFEC | Pointer to the first transaction on the Future Events Chain (FTFEC=X(28)). |
| FTRA | Pointer to the first transaction on the list of unused transactions. |
| FUNCT | Pointer to the word preceding the function directory in the X-vector (FUNCT=X(17)). |
| FW* | See FWORD(*). |
| FWORD(*) | Integer*4 temporary variable (FW*=FWORD(*); FWORD(1)=DWORD(1)). |
| GBITS | Function which returns value of bits specified. |
| GIVEUP | Number of storage units being made available. |
| HIGH | Ending entity number to be used in SELECT block search. |
| HW* | See HWORD(*). |
| HWORD(*) | Integer*2 temporary variable (HW*=HWORD(*); HWORD(1)=DWORD(1)). |
| IDT | Identification number of entity to be used when calling SPSTAT. |
| IMAX | Looping limit for outputing the OS stack when tracing argument evaluations. |
| INST | Pointer to current block element being processed. |
| INTDEC(*) | Indicates whether corresponding OS/FOS value is integer or floating point. |
| IORD | Indicates whether value returned by SPSTAT is integer or decimal. |
| JBL | Number of the block whose routine is being executed. |
| KDEX | Index used to keep count of number of arguments specified for a block. |

| | |
|---|---|
| KMODE | Special mode variable used to determine how a function is to be evaluated. |
| KOUNT | Counter used as index into function entity tables. |
| KXVAL | Integer*4 value of independent variable used in function computation. |
| KYVAL | Integer*4 value of dependent variable used in function computation. |
| LB | Specifies the last bit to be set in a call to PBITS. |
| LOW | Beginning entity number to be used in SELECT block search. |
| LTCEC | Pointer to the last transaction on the Current Events Chain (LTCEC=X(27)). |
| LTFEC | Pointer to the last transaction on the Future Events Chain (LTFEC=X(29)). |
| MAXCTS | Maximum contents of a storage or queue. |
| MAXX | Maximum number of X-vector elements. |
| MDFR | Modifier used in TEST, SELECT, GATE, and ASSIGN blocks. |
| MODE | Indicates whether simulation will begin in Simulate/Start, Reset, Clear, or Start mode (MODE=X(1)). |
| MRNG | Number of points in a function. |
| NBLO | Number of blocks (NBLO=X(18)). |
| NEWBDT | Block departure time of transaction being merged into the FEC. |
| NEWPRI | Priority of transaction being merged into the CEC. |

| | |
|---|---|
| NEXBDT | Block departure time of first transaction on the FEC. |
| NEXBLO | Next block number transaction is to enter. |
| NFUNCT | Number of functions (NFUNCT=X(16)). |
| NOUPD | Indicator used to merge a transaction into the CEC without updating the clock. |
| NPAR | Number of transaction parameters (NPAR=X(24)). |
| NQUE | Number of queues (NQUE=X(14)). |
| NSAV | Number of savevalues (NSAV=X(22)). |
| NSTO | Number of storages (NSTO=X(12)). |
| NTAB | Number of tables (NTAB=X(20)). |
| NVAR | Number of GPSS-type variables (NVAR=X(31)). |
| OLDBDT | Block departure time of transaction being checked in the FEC. |
| OLDPRI | Priority of transaction being checked in the CEC. |
| OPCODE | Operation code indicating type of block. |
| OS(*) | Stack for evaluating integer arguments (OS(*)=FOS(*)). |
| OUTX | Specifies optional output file for X-vector (defaults to 0 (no output)). |
| OUT6 | Specifies optional output file for traces and SIMOUT output (defaults to 6 (terminal)). |
| PBITS | Subroutine called to turn on specified bits in an indicator. |
| PCONTS | Present contents of a queue. |

| | |
|---|---|
| PNTA | Pointer to last entry on return address stack. |
| PNTB | Pointer to last evaluated argument on OS/FOS stack. |
| PNTF | Pointer to the first element of the frequency intervals for a table entity. |
| PNTS | Pointer to the first element of the slope values of the current function entity. |
| PNTT | Pointer to the transaction being compared with the current transaction. |
| PNTX | Pointer to the first element of the independent variable values of the current function entity. |
| PNTY | Pointer to the first element of the function values of the current function entity. |
| PR(*) | Temporary vector to save integer values in the OS stack for output while tracing. |
| QUE | Pointer to the word preceding the queue directory in the X-vector (QUE=X(15)). |
| RAS | Return address stack used to temporarily hold the location of the next arguments to be evaluated. |
| RN | Random number. |
| ROW | Argument to SETIND which specifies which status switch row is being set. |
| RR* | Temporary real*4 variables used primarily to save values for immediate output. |
| RSLOPE | Slope used in function evaluation. |
| RTERM | Specifies optional input file for entering optional data (defaults to 5 (terminal)). |
| RVAL | Value to be returned by SPSTAT if real*4 result is required. |

| | |
|---|---|
| RX(*) | Variable used to manipulate real*4 values in the X-vector (RX(*)=X(*)). |
| RXVAL | Real*4 value of the independent variable used in function computation. |
| RYVAL | Real*4 value of the dependent variable used in function computation. |
| SAVE | Pointer to the word preceding savevalue locations in the X-vector (SAVE=X(23)). |
| SCFLAG | Status change flag. Restarts scan at the beginning of the CEC when on. |
| SE | Pointer to the top of the pushdown chain for storage empty condition. |
| SEED(*) | Seed used in random number generation (SEED(1-8)=X(3-10)). |
| SETIND | Entry point. Called to set status switch indicators. |
| SF | Pointer to top of pushdown chain for storage full condition. |
| SIMOUT | Entry point. Called to output GPSS-like statistics. |
| SNA | Specifies the Standard Numerical Attribute to be evaluated on call to SPSTAT. |
| SNE | Pointer to the top of the pushdown chain for storage not empty condition. |
| SNF | Pointer to the top of the pushdown chain for storage not full condition. |
| SPSTAT | Entry point. Called to output special statistics (individual SNA's). |
| SRED | Pointer to the top of the pushdown chain for storage reduction in contents condition. |

| | |
|---|---|
| SSIND | Scan status indicator. True if the transaction is in an active status on the CEC. |
| STATSW(*) | Vector containing status switches which indicate which statistics are to be output by the SIMOUT routine. |
| STO | Pointer to the word preceding the storage directory in the X-vector (STO=X(13)). |
| TAB | Pointer to the word preceding the table directory in the X-vector (TAB=X(21)). |
| TASGN | The value being assigned in an ASSIGN block. |
| TBLNO | Number of table being tabulated. |
| TBLO | Temporary variable used to save the pointer to the current block. |
| TCNT | Temporary location for saved termination count in TERMINATE block. |
| TCTRA | Temporary variable for saving the pointer to the current transaction. |
| TEMP* | Temporary integer*4 variable. |
| TEST | Value of pointers associated with the delay chains. |
| TPAR | Parameter being assigned a value in an ASSIGN block. |
| TRACE | Logical switch for tracing simulation mode. |
| TRAN | Pointer to the word preceding the transaction entities (TRAN=X(25)). |
| TRARG | Logical switch for tracing argument evaluation. |
| TRBLO | Logical switch for tracing block routines. |
| TRCNT | Indicates the transaction number being assigned a new transaction. |

| | |
|---|---|
| TRMCNT | Termination count (TRMCNT=X(2)). |
| TRSCN | Logical switch for tracing scan procedure. |
| TRSIZE | Indicates the size of the X-vector printout. |
| TRS1 | Logical switch for tracing chain manipulations. |
| TRTN | Temporary variable used to save the ZRTN value. |
| TRUPD | Logical switch for tracing update clock procedure. |
| TR6 | Logical trace enable switch. |
| TTRA | Temporary variable used to save the pointer to the current transaction. |
| TYPARG | Indicates whether the search argument of a function entity is integer or floating point. |
| TYPX | Indicates whether the independent variable of a function entity is integer or floating point. |
| TYPY | Indicates whether the function values of a function entity are integer or floating point. |
| ULLI | Indicates the upper limit of the lowest frequency interval for a table entity. |
| UNITS | Number of units entering or leaving a queue. |
| USED | Current contents of a storage entity. |
| VAL | Value to be returned by SPSTAT as an integer*4. |
| VAR | Pointer to the word preceding the variable directory in the X-vector (VAR=X(32)). |
| WANT | Number of storage units required. |
| WRTN | Temporary variable used to save the ZRTN value. |

| | |
|---|---|
| WTERM | Specifies optional output file (defaults to 6 (terminal)). |
| WTFAC | Weighting factor utilized in TABULATE block. Defaults to one if not specified. |
| X(*) | Vector used for holding all storages, queues, tables, directories, etc. |
| ZRTN | Holds statement number for use in returning from various routines. |

## APPENDIX C

```
C          ********** SIMULT *** SPSTAT *** SIMOUT *** SETIND **********

      SUBROUTINE SIMULT(TR6,OUT6,RTERM,WTERM)                           SIM00010
      IMPLICIT INTEGER(A-Q,S-Z),REAL(R)                                 SIM00020
      INTEGER*4 X(200),FWORD(4),RAS(10),OS(20),SEED(8),RTERM            SIM00030
      INTEGER*2 HWORD(8),CTRA,FTRA,ZRTN,PNTA,PNTB,PNTT,INTDEC(20),PNTF, SIM00040
     -INST,PNTX,PNTY,PNTS,WRTN,TYPX,TYPY,CBLO,NEXBLO,MDFR,              SIM00050
     -HW1,HW2,HW3,HW4,HW5,HW6,HW7,HW8,EPT                               SIM00060
      REAL*8 DWORD(2),DW1,DW2                                           SIM00070
      REAL*4 FFWORD(4),FOS(20),RX(1000),FFW1,FFW2,FFW3,FFW4             SIM00080
      LOGICAL*1 BYTE(16),SSIND                                          SIM00090
      LOGICAL TR6,TRACE,TRARG,TRBLO,TRUPD,TRSCN,TRULK,TRS1              SIM00100
      COMMON /XVECTR/ MAXX,X                                            SIM00110
      EQUIVALENCE(DWORD,FWORD,FFWORD,HWORD,BYTE),(DWORD(1),DW1),        SIM00130
     -(DWORD(2),DW2),                                                   SIM00140
     -(FWORD(1),FW1),(FWORD(2),FW2),(FWORD(3),FW3),(FWORD(4),FW4),      SIM00150
     -(FFWORD(1),FFW1),(FFWORD(2),FFW2),(FFWORD(3),FFW3),               SIM00160
     -(FFWORD(4),FFW4),                                                 SIM00170
     -(HWORD(1),HW1),(HWORD(2),HW2),(HWORD(3),HW3),(HWORD(4),HW4),      SIM00180
     -(HWORD(5),HW5),(HWORD(6),HW6),(HWORD(7),HW7),(HWORD(8),HW8),      SIM00190
     -(X(1),MODE),(X(2),TRMCNT),(X(3),SEED),(X(11),CLOCK),(X(12),NSTO), SIM00200
     -(X(13),STO),(X(14),NQUE),(X(15),QUE),(X(16),NFUNCT),(X(17),FUNCT),SIM00210
     -(X(18),NBLO),(X(19),BLOCK),(X(20),NTAB),(X(21),TAB),(X(22),NSAV), SIM00220
     -(X(23),SAVE),(X(24),NPAR),(X(25),TRAN),(X(26),FTCEC),             SIM00230
     -(X(27),LTCEC),(X(28),FTFEC),(X(29),LTFEC),(X(30),ERR),            SIM00240
     -(X(31),NVAR),(X(32),VAR),                                         SIM00250
     -(X,RX),(OS,FOS)                                                   SIM00260
      NAMELIST/P/ TRACE,TRARG,TRBLO,TRUPD,TRSCN,TRULK,OUTX,TRSIZE,TRS1  SIM00270


C                                       ***** SIMULT *****

C                                       INITIALIZE OPTIONAL TRACES
      TRACE=.FALSE.                                                     SIM00340
      TRARG=.FALSE.                                                     SIM00350
      TRBLO=.FALSE.                                                     SIM00360
      TRUPD=.FALSE.                                                     SIM00370
      TRSCN=.FALSE.                                                     SIM00380
      TRULK=.FALSE.                                                     SIM00390
      TRS1=.FALSE.                                                      SIM00400
      OUTX=0                                                            SIM00420
      TRSIZE=MAXX                                                       SIM00430
      IF(TR6) WRITE(WTERM,9025)                                         SIM00440
      IF(TR6) READ(RTERM,P)                                             SIM00450
```

```
C                                         SET ENTRY POINT AND BRANCH
C                                         TO APPROPRIATE MODE
      EPT=1                                                            SIM00460
      PNTT=0                                                           SIM00470
      IF (MODE.EQ.4) GO TO 400                                         SIM00480
      IF(MODE.EQ.2) GOTO 60                                            SIM00490
      CLOCK=0                                                          SIM00510
      CLOCKB=0                                                         SIM00530
      IF(MODE.EQ.3) GOTO 40                                            SIM00540
C                                         *** BEGIN NEW SIMULATION ***
      IF(TRACE) WRITE(OUT6,9003)                                       SIM00550
C                                         SLOPE COMPUTATION
      IF(TRACE) WRITE(OUT6,9002)                                       SIM00570
      K=0                                                              SIM00580
   20 IF(K.GE.NFUNCT) GOTO 25                                          SIM00590
      K=K+1                                                            SIM00600
      PNTF=X(FUNCT+K)                                                  SIM00610
      FW1=X(PNTF+5)                                                    SIM00620
      IF(HW1.GE.2) GOTO 25                                             SIM00630
      MRNG=HW2                                                         SIM00640
      PNTX=PNTF+6                                                      SIM00650
      PNTY=PNTX+MRNG                                                   SIM00660
      PNTS=PNTY+MRNG                                                   SIM00670
      FW1=X(PNTX)                                                      SIM00680
      TYPX=HW1                                                         SIM00690
      TYPY=HW2                                                         SIM00700
      RX(PNTS+1)=0.0                                                   SIM00710
      DO 22 I=2,MRNG                                                   SIM00720
      RXVAL=X(PNTX+I)-X(PNTX+I-1)                                      SIM00730
      IF(TYPX.EQ.1) RXVAL=RX(PNTX+I)-RX(PNTX+I-1)                      SIM00735
      RYVAL=X(PNTY+I)-X(PNTY+I-1)                                      SIM00740
      IF(TYPY.EQ.1) RYVAL=RX(PNTY+I)-RX(PNTY+I-1)                      SIM00750
      RX(PNTS+I)=RYVAL/RXVAL                                           SIM00800
   22 CONTINUE                                                         SIM00810
      GOTO 20                                                          SIM00820
C                                         CREATE CHAIN OF UNUSED TRANS
   25 FTRA=TRAN                                                        SIM00840
      KK=MAXX-TRAN                                                     SIM00880
      KK=KK/(8+NPAR)-1                                                 SIM00890
      LL=TRAN                                                          SIM00900
      DO 27 I=1,KK                                                     SIM00910
      HW1=0                                                            SIM00920
      HW2=LL+8+NPAR                                                    SIM00930
      X(LL+1)=FW1                                                      SIM00940
      LL=LL+8+NPAR                                                     SIM00950
   27 CONTINUE                                                         SIM00960
      X(LL+1)=0                                                        SIM00965
```

```
C                                             PLACE ALL GENERATE BLOCKS ON
C                                             FEC THEN JUMP TO SCAN
      TRCNT=0                                                           SIM01000
      JBL=0                                                             SIM01010
 30   IF(JBL.EQ.NBLO) GOTO 400                                          SIM01020
      JBL=JBL+1                                                         SIM01030
      CBLO=X(BLOCK+JBL)                                                 SIM01040
      FW1=X(CBLO+1)                                                     SIM01050
      OPCODE=HW1                                                        SIM01060
      IF(TRACE) WRITE(OUT6,9038) OPCODE                                 SIM01070
      IF(OPCODE.NE.1) GOTO 30                                           SIM01080
      INST=CBLO+2                                                       SIM01090
      ZRTN=32                                                           SIM01100
      GO TO 100                                                         SIM01110
 32   ZRTN=30                                                           SIM01120
      GOTO 200                                                          SIM01130

C                                             *** CLEAR ***
 40   IF(TRACE) WRITE(OUT6,9004)                                        SIM01150
      FTCEC=0                                                           SIM01160
      LTCEC=0                                                           SIM01170
      FTFEC=0                                                           SIM01180
      LTFEC=0                                                           SIM01190
C                                             CLEAR STORAGES
      IF(NSTO.EQ.0) GOTO 44                                             SIM01300
      DO 43 I=1,NSTO                                                    SIM01310
      N=X(STO+I)                                                        SIM01320
      IF (N.EQ.0) GO TO 43                                              SIM01325
      X(N+2)=X(N+2)+X(N+1)                                              SIM01340
      X(N+1)=0                                                          SIM01330
      DW1=0.                                                            SIM01350
      X(N+3)=FW1                                                        SIM01360
      X(N+4)=FW2                                                        SIM01370
      X(N+5)=0                                                          SIM01380
      X(N+6)=0                                                          SIM01390
      X(N+7)=0                                                          SIM01400
 43   CONTINUE                                                          SIM01410
C                                             CLEAR QUEUES
 44   IF(NQUE.EQ.0) GOTO 48                                             SIM01420
      DO 47 I=1,NQUE                                                    SIM01430
      N=X(QUE+I)                                                        SIM01440
      IF (N.EQ.0) GO TO 47                                              SIM01445
      X(N+1)=0                                                          SIM01450
      X(N+2)=0                                                          SIM01460
      X(N+3)=0                                                          SIM01470
      DW1=0.                                                            SIM01480
      X(N+4)=FW1                                                        SIM01490
      X(N+5)=FW2                                                        SIM01500
```

```
      X(N+6)=0                                                          SIM01510
      X(N+7)=0                                                          SIM01520
   47 CONTINUE                                                          SIM01530
C                                  CLEAR SAVEVALUES
   48 IF(NSAV.EQ.0) GOTO 50                                             SIM01540
      DO 49 I=1,NSAV                                                    SIM01550
      X(SAVE+I)=0                                                       SIM01560
   49 CONTINUE                                                          SIM01570
C                                  CLEAR/RESET TABLES
   50 IF(NTAB.EQ.0) GOTO 58                                             SIM01580
      DO 56 I=1,NTAB                                                    SIM01590
      N=X(TAB+I)                                                        SIM01600
      IF (N.EQ.0) GO TO 56                                              SIM01605
      RX(N+1)=0.0                                                       SIM01610
      RX(N+2)=0.0                                                       SIM01620
      RX(N+3)=0.0                                                       SIM01630
      RX(N+4)=0.0                                                       SIM01640
      X(N+5)=0                                                          SIM01645
      RX(N+7)=0.0                                                       SIM01650
      K=X(N+8)                                                          SIM01660
      DO 55 J=1,K                                                       SIM01670
      X(N+ 9+J)=0                                                       SIM01680
   55 CONTINUE                                                          SIM01690
   56 CONTINUE                                                          SIM01695
C                                  CLEAR/RESET COMPLETED
   58 GOTO(59,400,25),MODE                                              SIM01700
   59 CALL ERRORZ(603,1,&9999)                                          SIM01710

C                                  *** RESET ***
   60 CLOCKB=CLOCK                                                      SIM01740
      IF(TRACE) WRITE(OUT6,9005)                                        SIM01750
C                                  RESET STORAGES
      IF(NSTO.EQ.0) GOTO 63                                             SIM01760
      DO 62 I=1,NSTO                                                    SIM01770
      N=X(STO+I)                                                        SIM01780
      IF (N.EQ.0) GO TO 62                                              SIM01785
      DW1=0.                                                            SIM01790
      X(N+3)=FW1                                                        SIM01800
      X(N+4)=FW2                                                        SIM01810
      X(N+5)=CLOCK                                                      SIM01820
      X(N+6)=X(N+1)                                                     SIM01830
      X(N+7)=X(N+1)                                                     SIM01840
   62 CONTINUE                                                          SIM01850
C                                  RESET QUEUES
   63 IF(NQUE.EQ.0) GOTO 50                                             SIM01860
      DO 67 I=1,NQUE                                                    SIM01870
      N=X(QUE+I)                                                        SIM01880
      IF (N.EQ.0) GO TO 67                                              SIM01885
```

```
      X(N+1)=CLOCK
      DW1=0.
      X(N+4)=FW1
      X(N+5)=FW2
      X(N+2)=X(N+6)
      X(N+3)=0
      X(N+7)=X(N+6)
 67   CONTINUE
      GOTO 50
C                                      *** ARGUMENT EVALUATION ***
 100  PNTA=0
      PNTB=0
      IF(TRARG) WRITE(OUT6,9006)
 1001 FW1=X(INST)
      IF(HW1.GE.0) GOTO 196
      IF(HW2) 1002,1004,1003
 1002 HW2=-HW2
      IF(HW2.GT.NPAR) CALL ERRORZ(492,1,&9999)
      IF(HW2.LE.0) CALL ERRORZ(492,2,&9999)
      HW2=X(CTRA+8+HW2)
 1003 HW1=-HW1
 1006 GOTO (101,102,103,104,105,106,107,108,109,
     -110,111,112,113,114,115,116,117,118,119,
     -120,121,122,123,124,125,126,127,128,129,
     -130,199,199,133),HW1
 1004 IF(HW1.EQ.-33) GOTO 133
      IF(HW1.EQ.-23) GOTO 123
      IF(HW1.EQ.-25) GOTO 125
      FW2=X(CBLO+1)
      IF(HW3.NE.21.OR.PNTB.NE.4) GOTO 1005
      HW2=1
      GOTO 1003
 1005 CALL ERRORZ(45,0,&9999)
C                                      P
 101  FW1=X(CTRA+8+HW2)
      GO TO 190
C                                      PR
 102  FW1=X(CTRA+5)
      HW1=0
      GOTO 190
C                                      M1
 103  FW1=CLOCK-X(CTRA+4)
      GOTO 190
C                                      MP
 104  FW1=CLOCK-X(CTRA+8+HW2)
      GOTO 190
C                                      SC
```

```
 105  IF(HW2.GT.NSTO) CALL ERRORZ(499,0,&9999)                    SIM02360
      N=X(STO+HW2)                                                SIM02370
      FW1=X(N+6)                                                  SIM02380
      GOTO 190                                                    SIM02390
C                                        SM
 106  IF(HW2.GT.NSTO) CALL ERRORZ(499,0,&9999)                    SIM02410
      N=X(STO+HW2)                                                SIM02420
      FW1=X(N+7)                                                  SIM02430
      GOTO 190                                                    SIM02440
C                                        SR
 107  IF(HW2.GT.NSTO) CALL ERRORZ(499,0,&9999)                    SIM02460
      N=X(STO+HW2)                                                SIM02470
      FW3=X(N+3)                                                  SIM02480
      FW4=X(N+4)                                                  SIM02490
      FW1=X(N+1)+X(N+2)                                           SIM02500
      FW1=FW1*CLOCK                                               SIM02510
      RVAL=DW2/FW1                                                SIM02520
      FW1=(DW2/FW1)*1000                                          SIM02530
      GOTO 190                                                    SIM02540
C                                        SA
 108  IF(HW2.GT.NSTO) CALL ERRORZ(499,0,&9999)                    SIM02560
      N=X(STO+HW2)                                                SIM02570
      FW3=X(N+3)                                                  SIM02580
      FW4=X(N+4)                                                  SIM02590
      FW1=DW2/CLOCK                                               SIM02600
      RVAL=DW2/CLOCK                                              SIM02610
      GOTO 190                                                    SIM02620
C                                        S
 109  IF(HW2.GT.NSTO) CALL ERRORZ(499,0,&9999)                    SIM02640
      N=X(STO+HW2)                                                SIM02650
      FW1=X(N+1)                                                  SIM02660
      GOTO 190                                                    SIM02670
C                                        R
 110  IF(HW2.GT.NSTO) CALL ERRORZ(499,0,&9999)                    SIM02690
      N=X(STO+HW2)                                                SIM02700
      FW1=X(N+2)                                                  SIM02710
      GOTO 190                                                    SIM02720
C                                        ST
 111  IF(HW2.GT.NSTO) CALL ERRORZ(499,0,&9999)                    SIM02740
      N=X(STO+HW2)                                                SIM02750
      FW3=X(N+3)                                                  SIM02760
      FW4=X(N+4)                                                  SIM02770
      FW1=0                                                       SIM02780
      IF (X(N+6).EQ.0) GO TO 190                                  SIM02790
      FW1=DW2/X(N+6)                                              SIM02800
      RVAL=DW2/X(N+6)                                             SIM02810
      GOTO 190                                                    SIM02820
C                                        Q
```

```
  112 IF(HW2.GT.NQUE) CALL ERRORZ(500,0,&9999)                    SIM02840
      N=X(QUE+HW2)                                                SIM02850
      FW1=X(N+6)                                                  SIM02860
      GOTO 190                                                    SIM02870
C                                         QA
  113 IF(HW2.GT.NQUE) CALL ERRORZ(500,0,&9999)                    SIM02890
      N=X(QUE+HW2)                                                SIM02900
      FW3=X(N+4)                                                  SIM02910
      FW4=X(N+5)                                                  SIM02920
      FW1=DW2/CLOCK                                               SIM02930
      RVAL=DW2/CLOCK                                              SIM02940
      GOTO 190                                                    SIM02950
C                                         QM
  114 IF(HW2.GT.NQUE) CALL ERRORZ(500,0,&9999)                    SIM02970
      N=X(QUE+HW2)                                                SIM02980
      FW1=X(N+7)                                                  SIM02990
      GOTO 190                                                    SIM03000
C                                         QC
  115 IF(HW2.GT.NQUE) CALL ERRORZ(500,0,&9999)                    SIM03020
      N=X(QUE+HW2)                                                SIM03030
      FW1=X(N+2)                                                  SIM03040
      GOTO 190                                                    SIM03050
C                                         QZ
  116 IF(HW2.GT.NQUE) CALL ERRORZ(500,0,&9999)                    SIM03070
      N=X(QUE+HW2)                                                SIM03080
      FW1=X(N+3)                                                  SIM03090
      GOTO 190                                                    SIM03100
C                                         QT
  117 IF(HW2.GT.NQUE) CALL ERRORZ(500,0,&9999)                    SIM03120
      N=X(QUE+HW2)                                                SIM03130
      FW3=X(N+4)                                                  SIM03140
      FW4=X(N+5)                                                  SIM03150
      FW1=0                                                       SIM03160
      IF (X(N+2).EQ.0) GO TO 190                                  SIM03170
      FW1=DW2/X(N+2)                                              SIM03180
      RVAL=DW2/X(N+2)                                             SIM03190
      GOTO 190                                                    SIM03200
C                                         QX
  118 IF(HW2.GT.NQUE) CALL ERRORZ(500,0,&9999)                    SIM03220
      N=X(QUE+HW2)                                                SIM03230
      FW3=X(N+4)                                                  SIM03240
      FW4=X(N+5)                                                  SIM03250
      FW1=X(N+2)-X(N+3)                                           SIM03260
      IF (FW1.EQ.0) GO TO 190                                     SIM03270
      RVAL=DW2/FW1                                                SIM03280
      FW1=DW2/FW1                                                 SIM03290
      GOTO 190                                                    SIM03300
C                                         TB
```

```
  119 IF(HW2.GT.NTAB) CALL ERRORZ(435,0,&9999)                SIM03320
      N=X(TAB+HW2)                                            SIM03330
      FFW1=0.                                                 SIM03340
      IF (X(N+5).EQ.0) GO TO 190                              SIM03350
      FFW1=RX(N+1)/X(N+5)                                     SIM03360
      RVAL=FFW1                                               SIM03370
      GOTO 190                                                SIM03380
C                                         TC
  120 IF(HW2.GT.NTAB) CALL ERRORZ(435,0,&9999)                SIM03400
      N=X(TAB+HW2)                                            SIM03410
      FW1=X(N+5)                                              SIM03420
      GOTO 190                                                SIM03430
C                                         TD
  121 IF(HW2.GT.NTAB) CALL ERRORZ(435,0,&9999)                SIM03450
      N=X(TAB+HW2)                                            SIM03460
      FFW1=0.                                                 SIM03470
      IF (X(N+5).LE.1) GO TO 190                              SIM03480
      FFW1=RX(N+2)-(RX(N+1)**2)/X(N+5)                        SIM03490
      FFW1=SQRT(FFW1/(X(N+5)-1))                              SIM03500
      RVAL=FFW1                                               SIM03510
      GOTO 190                                                SIM03520
C                                         FN
  122 IF(HW2.GT.NFUNCT) CALL ERRORZ(507,0,&9999)              SIM03540
      PNTA=PNTA+1                                             SIM03550
      RAS(PNTA)=INST+1                                        SIM03560
      INST=X(FUNCT+HW2)+1                                     SIM03570
      GOTO 1001                                               SIM03580
  123 FW1=X(INST+3)                                           SIM03590
      MRNG=HW2                                                SIM03600
      PNTX=INST+4                                             SIM03610
      PNTY=PNTX                                               SIM03620
      IF(HW1.LE.3) PNTY=PNTY+MRNG                             SIM03630
      PNTS=PNTY+MRNG                                          SIM03640
      KARG=OS(PNTB)                                           SIM03650
      RKARG=FOS(PNTB)                                         SIM03660
      TYPARG=INTDEC(PNTB)                                     SIM03670
      KMODE=2*(HW1-1)+TYPARG+1                                SIM03680
      FW2=X(INST+4)                                           SIM03690
      TYPX=HW3                                                SIM03700
      TYPY=HW4                                                SIM03710
      IF(KMODE.GT.7) GOTO 1235                                SIM03720
      KCUNT=0                                                 SIM03730
      IF(TYPX.EQ.0) GOTO 1232                                 SIM03740
      IF(TYPARG.EQ.0) RKARG=KARG                              SIM03750
      DO 1231 I=1,MRNG                                        SIM03760
      KOUNT=KOUNT+1                                           SIM03770
      IF(RKARG.LE.RX(PNTX+KOUNT)) GO TO 1234                  SIM03780
 1231 CONTINUE                                                SIM03790
```

```
      GOTO 1234                                                         SIM03800
 1232 IF(TYPARG.EQ.1) KARG=RKARG                                        SIM03810
      DO 1233 I=1,MRNG                                                  SIM03820
      KOUNT=KOUNT+1                                                     SIM03830
      IF(KARG.LE.X(PNTX+KOUNT)) GOTO 1234                               SIM03840
 1233 CONTINUE                                                          SIM03850
 1234 IF(KMODE.LE.2) GOTO 1237                                          SIM03860
      KARG=KOUNT                                                        SIM03870
      TYPARG=0                                                          SIM03880
      KMODE=KMODE+4                                                     SIM03890
 1235 IF(TYPARG.EQ.1) KARG=RKARG                                        SIM03900
      IF(KARG.GT.MRNG) CALL ERRORZ(509,0,&9999)                         SIM03910
      IF(KARG.LT.1) CALL ERRORZ(509,0,&9999)                            SIM03920
      IF(KMODE.GE.9) GOTO 1236                                          SIM03930
      OS(PNTB)=X(PNTY+KARG)                                             SIM03940
      INTDEC(PNTB)=0                                                    SIM03950
      GOTO 1239                                                         SIM03960
 1236 X(INST+1)=X(PNTY+KARG)                                            SIM03970
      PNTB=PNTB-1                                                       SIM03980
      INST=INST+1                                                       SIM03990
      GOTO 1001                                                         SIM04000
 1237 KXVAL=X(PNTX+KOUNT-1)                                             SIM04010
      RXVAL=RX(PNTX+KOUNT-1)                                            SIM04020
      KYVAL=X(PNTY+KOUNT-1)                                             SIM04030
      RYVAL=RX(PNTY+KOUNT-1)                                            SIM04040
      RSLOPE=RX(PNTS+KOUNT)                                             SIM04050
      INTDEC(PNTB)=1                                                    SIM04060
      IF(KOUNT.EQ.1) KOUNT=2                                            SIM04070
      IF(KMODE.EQ.1) GOTO 1238                                          SIM04080
      FFW1=RX(PNTX+MRNG)                                                SIM04090
      IF(RKARG.GT.FFW1) RKARG=FFW1                                      SIM04100
      RXVAL=RKARG-RXVAL                                                 SIM04110
      RXVAL=RSLOPE*RXVAL                                                SIM04120
      FOS(PNTB)=RYVAL+RXVAL                                             SIM04130
      IF(TYPY.EQ.0) FOS(PNTB)=KYVAL+RXVAL                               SIM04140
      GOTO 1239                                                         SIM04150
 1238 FW1=X(PNTX+MRNG)                                                  SIM04160
      IF(KARG.GT.FW1) KARG=FW1                                          SIM04170
      KXVAL=KARG-KXVAL                                                  SIM04180
      RXVAL=RSLOPE*KXVAL                                                SIM04190
      FOS(PNTB)=RYVAL+RXVAL                                             SIM04200
      IF(TYPY.EQ.0) FOS(PNTB)=KYVAL+RXVAL                               SIM04210
 1239 INST=RAS(PNTA)                                                    SIM04220
      PNTA=PNTA-1                                                       SIM04230
      GOTO 1001                                                         SIM04240
C                                                 V
 124  IF(HW2.GT.NVAR) CALL ERRORZ(514,0,&9999)                          SIM04260
      PNTA=PNTA+1                                                       SIM04270
```

```
      RAS(PNTA)=INST+1                                                  SIM04280
      INST=X(VAR+HW2)+1                                                 SIM04290
      GOTO 1001                                                         SIM04300
  125 INST=RAS(PNTA)                                                    SIM04310
      PNTA=PNTA-1                                                       SIM04320
      IF(INTDEC(PNTB).EQ.0) GOTO 1001                                   SIM04330
      OS(PNTB)=FOS(PNTB)                                                SIM04340
      INTDEC(PNTB)=0                                                    SIM04350
      GOTO 1001                                                         SIM04360
C                                  RN
  126 IF(HW2.GT.8) CALL ERRORZ(45,0,&9999)                              SIM04380
      SEED(HW2)=SEED(HW2)*65539                                         SIM04390
      RN=0.5+SEED(HW2)*0.2328306E-9                                     SIM04400
      IF(PNTA.EQ.0) GOTO 1261                                           SIM04410
      FW1=X(RAS(PNTA)-1)                                                SIM04420
      IF(HW1.NE.-22) GOTO 1261                                          SIM04430
      PNTB=PNTB+1                                                       SIM04440
      FOS(PNTB)=RN                                                      SIM04450
      INTDEC(PNTB)=1                                                    SIM04460
      GOTO 191                                                          SIM04470
 1261 FW1=1000.*RN                                                      SIM04480
      GOTO 190                                                          SIM04490
C                                  C1
  127 FW1=CLOCK-CLOCKB                                                  SIM04510
      GOTO 190                                                          SIM04520
C                                  X
  128 FW1=X(SAVE+HW2)                                                   SIM04540
      GOTO 190                                                          SIM04550
C                                  QP (PERCENT ZEROES)
  129 IF (HW2.GT.NQUE) CALL ERRORZ(500,0,&9999)                         SIM04570
      N=X(QUE+HW2)                                                      SIM04580
      RVAL=0.                                                           SIM04590
      IF (X(N+2).NE.0) RVAL=(100.*X(N+3))/X(N+2)                        SIM04600
      GOTO 190                                                          SIM04610
C                                  ARITHMETIC
  130 PNTB=PNTB-1                                                       SIM04630
      K=4*(HW2-1)+2*INTDEC(PNTB)+INTDEC(PNTB+1)+1                       SIM04640
      GOTO (1301,1302,1303,1304,1305,1306,1307,1308,1309,1310,1311,     SIM04650
     -1312,1313,1314,1315,1316,1317,1318,1319,1320),K                   SIM04660
 1301 OS(PNTB)=OS(PNTB)+OS(PNTB+1)                                      SIM04670
      GOTO 1321                                                         SIM04680
 1302 FOS(PNTB)=OS(PNTB)+FOS(PNTB+1)                                    SIM04690
      GOTO 1322                                                         SIM04700
 1303 FOS(PNTB)=FOS(PNTB)+OS(PNTB+1)                                    SIM04710
      GOTO 1322                                                         SIM04720
 1304 FOS(PNTB)=FOS(PNTB)+FOS(PNTB+1)                                   SIM04730
      GOTO 1322                                                         SIM04740
 1305 OS(PNTB)=OS(PNTB)-OS(PNTB+1)                                      SIM04750
```

```
      GOTO 1321                                                         SIM04760
 1306 FOS(PNTB)=OS(PNTB)-FOS(PNTB+1)                                    SIM04770
      GOTO 1322                                                         SIM04780
 1307 FOS(PNTB)=FOS(PNTB)-OS(PNTB+1)                                    SIM04790
      GOTO  1322                                                        SIM04800
 1308 FOS(PNTB)=FOS(PNTB)-FOS(PNTB+1)                                   SIM04810
      GOTO 1322                                                         SIM04820
 1309 OS(PNTB)=OS(PNTB)*OS(PNTB+1)                                      SIM04830
      GO TO 1321                                                        SIM04840
 1310 FOS(PNTB)=OS(PNTB)*FCS(PNTB+1)                                    SIM04850
      GOTO 1322                                                         SIM04860
 1311 FOS(PNTB)=FOS(PNTB)*OS(PNTB+1)                                    SIM04870
      GOTO 1322                                                         SIM04880
 1312 FOS(PNTB)=FOS(PNTB)*FOS(PNTB+1)                                   SIM04890
      GOTO 1322                                                         SIM04900
 1313 OS(PNTB)=OS(PNTB)/OS(PNTB+1)                                      SIM04910
      GOTO 1321                                                         SIM04920
 1314 FOS(PNTB)=OS(PNTB)/FOS(PNTB+1)                                    SIM04930
      GOTO 1322                                                         SIM04940
 1315 FOS(PNTB)=FOS(PNTB)/OS(PNTB+1)                                    SIM04950
      GOTO 1322                                                         SIM04960
 1316 FOS(PNTB)=FCS(PNTB)/FOS(PNTB+1)                                   SIM04970
      GOTO 1322                                                         SIM04980
 1317 OS(PNTB)=MOD(OS(PNTB),OS(PNTB+1))                                 SIM04990
      GOTO 1321                                                         SIM05000
 1318 FOS(PNTB)=AMOD(FLOAT(OS(PNTB)),FOS(PNTB+1))                       SIM05010
      GOTO 1322                                                         SIM05020
 1319 FOS(PNTB)=AMOD(FOS(PNTB),FLOAT(OS(PNTB+1)))                       SIM05030
      GOTO 1322                                                         SIM05040
 1320 FOS(PNTB)=AMOD(FOS(PNTB),FOS(PNTB+1))                             SIM05050
      GOTO 1322                                                         SIM05060
 1321 INTDEC(PNTB)=0                                                    SIM05070
      GOTO 191                                                          SIM05080
 1322 INTDEC(PNTB)=1                                                    SIM05090
      GOTO 191                                                          SIM05100
C                                  RETURN FROM ARG. EVALUATION
 133  MDFR=HW2                                                          SIM05120
      I=2                                                               SIM05130
      KDEX=PNTB                                                         SIM05140
 1331 IF(I.GT.PNTB) GOTO 1333                                           SIM05150
      IF(INTDEC(PNTB).EQ.0) GOTO 1332                                   SIM05160
      IF(I.EQ.2.AND.(OPCODE.EQ.1.OR.OPCODE.EQ.2)) GOTO 1332             SIM05170
      OS(I)=FOS(I)                                                      SIM05180
      INTDEC(I)=0                                                       SIM05190
 1332 I=I+1                                                             SIM05200
      GOTO 1331                                                         SIM05210
 1333 IF(PNTB.EQ.7) GOTO 1334                                           SIM05220
      PNTB=PNTB+1                                                       SIM05230
```

```
      OS(PNTB)=0
      INTDEC(PNTB)=0
      GOTO 1333
 1334 IF(.NOT.TRACE) GOTO 1337
      INTEGER*4 PR(7)
      IMAX=1
      DO 1335 I=1,7
      PR(I)=0
      IF(INTDEC(I).EQ.0) PR(I)=OS(I)
      IF(PR(I).NE.0) IMAX=I
 1335 CONTINUE
      IF(TRARG) WRITE(OUT6,9015) CBLO,OPCODE,MDFR,(PR(I),I=1,IMAX)
      DO 1336 I=1,7
      IF(INTDEC(I).EQ.1) WRITE(OUT6,9016) I,FOS(I)
 1336 CONTINUE
 1337 IF(ZRTN.EQ.32) GOTO 32
      IF(ZRTN.EQ.2316) GOTO 2316
      IF(ZRTN.EQ.4004) GOTO 4004
      CALL ERRORZ(603,6,&9999)
C                                           RETURN IF ENTRY POINT WAS SPSTAT
  190 IF (EPT.EQ.2) GO TO 5950
C                                           PLACE EVALUATED ARG. ON STACK
  196 PNTB=PNTB+1
      OS(PNTB)=FW1
      INTDEC(PNTB)=0
  191 INST=INST+1
      GOTO 1001
  199 CALL ERRORZ(45,0,&9999)

C                                           *** BLOCK ROUTINES ***
  200 IF(TRBLO) WRITE(OUT6,9007) OPCODE,CBLO
      GOTO (201,202,203,204,205,206,207,208,209,210,211,212,213,299,
     -299,216,299,299,299,299,221),OPCODE
C                                           GENERATE
  201 IF(KDEX.GE.4) GOTO 2014
      CTRA=FTRA
      FW1=X(CTRA+1)
      FTRA=HW2
      K=8+NPAR
      DO 2015 I=1,K
      X(CTRA+I)=0
 2015 CONTINUE
      IF(HW2.EQ.0) CALL ERRORZ(468,0,&9999)
      IF(TRBLO) WRITE(OUT6,9036) FTRA
      HW1=0
      HW2=JBL
      X(CTRA+1)=FW1
      TRCNT=TRCNT+1
```

```
      HW1=MDFR
      HW2=TRCNT
      X(CTRA+8)=FW1
      HW1=JBL+1
      HW2=OS(5)
      X(CTRA+5)=FW1
      BYTE(1)=.TRUE.
      BYTE(2)=.TRUE.
      HW2=0
      X(CTRA+6)=FW1
      FW1=X(CBLO+3)
      IF(KDEX.GE.2.AND.HW1.EQ.-22) GOTO 2011
      IF(OS(2).NE.0) GOTO 2013
      CREATE=OS(1)
      IF(INTDEC(1).EQ.1) CREATE=FOS(1)
      GOTO 2012
 2013 SEED(1)=SEED(1)*65539
      RN=0.5+SEED(1)*0.2328306E-9
      BASE=OS(1)-OS(2)
 2019 IF(BASE.LT.0) CALL ERRORZ(505,0,&9999)
      CREATE=BASE+(2*OS(2)*RN+0.5)
      GO TO 2012
 2011 BASE=OS(1)
      CREATE=BASE*OS(2)
      IF(INTDEC(2).EQ.1) CREATE=BASE*FOS(2)
 2012 X(CTRA+3)=CLOCK+CREATE
      X(CTRA+4)=X(CTRA+3)
      IF(TRBLO) WRITE(OUT6,9021) X(CTRA+3)
      IF(CREATE.NE.0) GOTO 3104
      NOUPD=1
      X(CTRA+2)=X(CTRA+1)
      GOTO 3001
 2014 NOUPD=0
      IF(ZRTN.EQ.2314) GOTO 2314
      IF(ZRTN.EQ.30) GOTO 30
      CALL ERRORZ(603,7,&9999)
C                                            ADVANCE
 202  FW1=X(CTRA+5)
      CBLO=X(BLOCK+HW1)
      FW1=X(CBLO+3)
      IF(HW1.EQ.-22) GOTO 2021
      SEED(1)=SEED(1)*65539
      RN=0.5+SEED(1)*0.2328306E-9
      BASE=OS(1)-OS(2)
      IF(BASE.LT.0) CALL ERRORZ(505,0,&9999)
      DELAY=BASE+(2*OS(2)*RN+0.5)
      GOTO 2022
 2021 BASE=OS(1)
```

```
      IF(INTDEC(1).EQ.1) BASE=FOS(1)                                    SIM06190
      IF(INTDEC(2).EQ.1) DELAY=BASE*FOS(2)                              SIM06200
 2022 X(CTRA+3)=CLOCK+DELAY                                             SIM06210
      GOTO 230                                                          SIM06220
C                                  TRANSFER
 203  NEXBLO=OS(2)                                                      SIM06240
      IF(NEXBLO.EQ.0) NEXBLO=OS(1)                                      SIM06250
      IF(NEXBLO.LT.1.OR.NEXBLO.GT.NBLO) CALL ERRORZ(603,8,&9999)        SIM06260
      GOTO 231                                                          SIM06270
C                                  ASSIGN
 204  TPAR=OS(1)                                                        SIM06290
      TASGN=OS(2)                                                       SIM06300
      IF(TPAR.GT.NPAR) CALL ERRORZ(492,0,&9999)                         SIM06310
      IF(KDEX.LE.2) GOTO 2042                                           SIM06320
      TASGN=TASGN*OS(3)                                                 SIM06330
      IF(INTDEC(3).EQ.1) TASGN=TASGN*FOS(3)                             SIM06340
 2042 IF(MDFR-2) 2043,2044,2045                                         SIM06350
 2043 X(CTRA+8+TPAR)=X(CTRA+8+TPAR)-TASGN                               SIM06360
      GOTO 2046                                                         SIM06370
 2044 X(CTRA+8+TPAR)=TASGN                                              SIM06380
      GOTO 2046                                                         SIM06390
 2045 X(CTRA+8+TPAR)=X(CTRA+8+TPAR)+TASGN                               SIM06400
 2046 GOTO 230                                                          SIM06410
C                                  MARK
 205  IF(OS(1).GT.NPAR) CALL ERRORZ(492,0,&9999)                        SIM06430
      IF(OS(1).EQ.0) GOTO 2051                                          SIM06440
      X(CTRA+8+OS(1))=CLOCK                                             SIM06450
      GOTO 230                                                          SIM06460
 2051 X(CTRA+4)=CLOCK                                                   SIM06470
      GOTO 230                                                          SIM06480
C                                  ENTER
 206  IF(OS(1).GT.NSTO) CALL ERRORZ(499,0,&9999)                        SIM06500
      CSTO=X(STO+OS(1))                                                 SIM06510
      AVAIL=X(CSTO+2)                                                   SIM06520
      WANT=OS(2)                                                        SIM06530
      IF(WANT.EQ.0) WANT=1                                              SIM06540
      IF(WANT.GT.AVAIL) GOTO 2064                                       SIM06550
      USED=X(CSTO+1)                                                    SIM06560
      PCONTS=USED                                                       SIM06570
      USED=USED+WANT                                                    SIM06580
      AVAIL=AVAIL-WANT                                                  SIM06590
      MAXCTS=X(CSTO+7)                                                  SIM06600
      IF(USED.GT.MAXCTS) X(CSTO+7)=USED                                 SIM06610
      X(CSTO+1)=USED                                                    SIM06620
      X(CSTO+2)=AVAIL                                                   SIM06630
      X(CSTO+6)=X(CSTO+6)+WANT                                          SIM06640
      DTIME=CLOCK-X(CSTO+5)                                             SIM06650
      X(CSTO+5)=CLOCK                                                   SIM06660
```

```
      FW1=X(CSTO+3)                                                     SIM06670
      FW2=X(CSTO+4)                                                     SIM06680
      DW1=DW1+DTIME*PCONTS                                              SIM06690
      X(CSTO+3)=FW1                                                     SIM06700
      X(CSTO+4)=FW2                                                     SIM06710
      FW1=X(CSTO+8)                                                     SIM06720
      SF=HW1                                                            SIM06730
      SNE=HW2                                                           SIM06740
      IF(SF.EQ.0.OR.AVAIL.NE.0) GOTO 2063                               SIM06750
      TEST=SF                                                           SIM06760
      SF=0                                                              SIM06770
 2061 IF(TEST.EQ.0) GOTO 2062                                           SIM06780
      FW1=X(TEST+6)                                                     SIM06790
      BYTE(2)=.TRUE.                                                    SIM06800
      X(TEST+6)=FW1                                                     SIM06810
      FW1=X(TEST+1)                                                     SIM06820
      HW3=TEST                                                          SIM06830
      TEST=HW1                                                          SIM06840
      HW1=0                                                             SIM06850
      X(HW3+1)=FW1                                                      SIM06860
      GOTO 2061                                                         SIM06870
 2062 SCFLAG=1                                                          SIM06880
 2063 IF(SNE.EQ.0.OR.USED.EQ.0) GOTO 230                                SIM06890
      TEST=SNE                                                          SIM06900
      SNE=0                                                             SIM06910
      GOTO 2061                                                         SIM06920
 2064 FW1=X(CTRA+1)                                                     SIM06930
      FW2=X(CSTO+10)                                                    SIM06940
      HW1=HW3                                                           SIM06950
      HW3=CTRA                                                          SIM06960
      X(CTRA+1)=FW1                                                     SIM06970
      X(CSTO+10)=FW2                                                    SIM06980
      FW1=X(CTRA+6)                                                     SIM06990
      BYTE(2)=.FALSE.                                                   SIM07000
      X(CTRA+6)=FW1                                                     SIM07010
      GOTO 4002                                                         SIM07020
C                                                   LEAVE
 207  IF(OS(1).GT.NSTO) CALL ERRORZ(499,0,&9999)                        SIM07040
      CSTO=X(STO+OS(1))                                                 SIM07050
      USED=X(CSTO+1)                                                    SIM07060
      PCONTS=USED                                                       SIM07070
      GIVEUP=OS(2)                                                      SIM07080
      IF(GIVEUP.EQ.0) GIVEUP=1                                          SIM07090
      IF(GIVEUP.GT.USED) CALL ERRORZ(425,0,&9999)                       SIM07100
      AVAIL=X(CSTO+2)                                                   SIM07110
      USED=USED-GIVEUP                                                  SIM07120
      AVAIL=AVAIL+GIVEUP                                                SIM07130
      X(CSTO+1)=USED                                                    SIM07140
```

```
      X(CSTO+2)=AVAIL                                                   SIM07150
      DTIME=CLOCK-X(CSTO+5)                                             SIM07160
      X(CSTO+5)=CLOCK                                                   SIM07170
      FW1=X(CSTO+3)                                                     SIM07180
      FW2=X(CSTO+4)                                                     SIM07190
      DW1=DW1+DTIME*PCONTS                                              SIM07200
      X(CSTO+3)=FW1                                                     SIM07210
      X(CSTO+4)=FW2                                                     SIM07220
      FW1=X(CSTO+9)                                                     SIM07230
      SE=HW1                                                            SIM07240
      SNF=HW2                                                           SIM07250
      FW1=X(CSTO+10)                                                    SIM07260
      SRED=HW1                                                          SIM07270
      IF(SE.EQ.0.OR.USED.GT.0) GOTO 2073                                SIM07280
      TEST=SE                                                           SIM07290
      SE=0                                                              SIM07300
 2071 IF(TEST.EQ.0) GOTO 2072                                           SIM07310
      FW1=X(TEST+6)                                                     SIM07320
      BYTE(2)=.TRUE.                                                    SIM07330
      X(TEST+6)=FW1                                                     SIM07340
      FW1=X(TEST+1)                                                     SIM07350
      HW3=TEST                                                          SIM07360
      TEST=HW1                                                          SIM07370
      HW1=0                                                             SIM07380
      X(HW3+1)=FW1                                                      SIM07390
      GOTO 2071                                                         SIM07400
 2072 SCFLAG=1                                                          SIM07410
 2073 IF(SNF.EQ.0.OR.AVAIL.EQ.0) GOTO 2074                              SIM07420
      TEST=SNF                                                          SIM07430
      SNF=0                                                             SIM07440
      GOTO 2071                                                         SIM07450
 2074 IF(SRED.EQ.0.OR.GIVEUP.EQ.0) GOTO 230                             SIM07460
      TEST=SRED                                                         SIM07470
      SRED=0                                                            SIM07480
      GOTO 2071                                                         SIM07490
C                                             QUEUE
 208  IF(OS(1).GT.NQUE) CALL ERRORZ(500,0,&9999)                        SIM07510
      CQUE=X(QUE+OS(1))                                                 SIM07520
      UNITS=OS(2)                                                       SIM07530
      IF(UNITS.EQ.0) UNITS=1                                            SIM07540
      PCONTS=X(CQUE+6)                                                  SIM07550
      X(CQUE+2)=X(CQUE+2)+UNITS                                         SIM07560
      X(CQUE+6)=PCONTS+UNITS                                            SIM07570
      MAXCTS=X(CQUE+7)                                                  SIM07580
      IF(X(CQUE+6).GT.MAXCTS) X(CQUE+7)=X(CQUE+6)                       SIM07590
      DTIME=CLOCK-X(CQUE+1)                                             SIM07600
      X(CQUE+1)=CLOCK                                                   SIM07610
      FW1=X(CQUE+4)                                                     SIM07620
```

```
      FW2=X(CQUE+5)                                                     SIM07630
      DW1=DW1+DTIME*PCONTS                                              SIM07640
      X(CQUE+4)=FW1                                                     SIM07650
      X(CQUE+5)=FW2                                                     SIM07660
      FW1=X(CTRA+6)                                                     SIM07670
      HW2=OS(1)                                                         SIM07680
      X(CTRA+6)=FW1                                                     SIM07690
      X(CTRA+7)=CLOCK                                                   SIM07700
      GOTO 230                                                          SIM07710
C                                       DEPART
 209  IF(OS(1).GT.NQUE) CALL ERRORZ(500,0,&9999)                        SIM07730
      CQUE=X(QUE+OS(1))                                                 SIM07740
      UNITS=OS(2)                                                       SIM07750
      IF(UNITS.EQ.0) UNITS=1                                            SIM07760
      PCONTS=X(CQUE+6)                                                  SIM07770
      IF(UNITS.GT.X(CQUE+6)) CALL ERRORZ(428,0,&9999)                   SIM07780
      IF(X(CTRA+7).EQ.CLOCK) X(CQUE+3)=X(CQUE+3)+UNITS                  SIM07790
      X(CQUE+6)=X(CQUE+6)-UNITS                                         SIM07800
      DTIME=CLOCK-X(CQUE+1)                                             SIM07810
      X(CQUE+1)=CLOCK                                                   SIM07820
      FW1=X(CQUE+4)                                                     SIM07830
      FW2=X(CQUE+5)                                                     SIM07840
      DW1=DW1+DTIME*PCONTS                                              SIM07850
      X(CQUE+4)=FW1                                                     SIM07860
      X(CQUE+5)=FW2                                                     SIM07870
      GOTO 230                                                          SIM07880
C                                       TERMINATE
 210  IF(.NOT.TRBLO) GOTO 2105                                          SIM07900
      WRITE(OUT6,9041) TRMCNT                                           SIM07910
      KK=8+NPAR                                                         SIM07920
      DO 2106 I=1,KK                                                    SIM07930
      FW1=X(CTRA+I)                                                     SIM07940
      WRITE(OUT6,9019) I,FW1,HW1,HW2                                    SIM07950
 2106 CONTINUE                                                          SIM07960
 2105 FW1=X(CTRA+2)                                                     SIM07970
      IF(HW1.EQ.0) GOTO 2102                                            SIM07980
      FW2=X(HW1+2)                                                      SIM07990
      HW4=HW2                                                           SIM08000
      X(HW1+2)=FW2                                                      SIM08010
 2101 IF(HW2.EQ.0) GOTO 2103                                            SIM08020
      FW2=X(HW2+2)                                                      SIM08030
      HW3=HW1                                                           SIM08040
      X(HW2+2)=FW2                                                      SIM08050
      GOTO 2104                                                         SIM08060
 2102 FTCEC=HW2                                                         SIM08070
      GOTO 2101                                                         SIM08080
 2103 LTCEC=HW1                                                         SIM08090
 2104 FW1=X(CTRA+1)                                                     SIM08092
```

```
      JBL=HW2                                                           SIM08094
      HW4=FTRA                                                          SIM08100
      X(CTRA+1)=FW2                                                     SIM08110
      FTRA=CTRA                                                         SIM08120
      TRMCNT=TRMCNT-OS(1)                                               SIM08130
      TCNT=TRMCNT                                                       SIM08132
      ZRTN=2108                                                         SIM08134
      GO TO 232                                                         SIM08136
 2108 IF (TCNT.LE.0) GO TO 9999                                         SIM08140
      GOTO 400                                                          SIM08160
C                                                   TEST
 211  GOTO (2111,2112,2113,2114,2115,2116),MDFR                         SIM08180
C                                                   TEST EQ
 2111 IF(OS(1).EQ.OS(2)) GOTO 230                                       SIM08200
      GOTO 2117                                                         SIM08210
C                                                   TEST LT
 2112 IF(OS(1).LT.OS(2)) GOTO 230                                       SIM08230
      GOTO 2117                                                         SIM08240
C                                                   TEST LE
 2113 IF(OS(1).LE.OS(2)) GOTO 230                                       SIM08260
      GOTO 2117                                                         SIM08270
C                                                   TEST GT
 2114 IF(OS(1).GT.OS(2)) GOTO 230                                       SIM08290
      GOTO 2117                                                         SIM08300
C                                                   TEST GE
 2115 IF(OS(1).GE.OS(2)) GOTO 230                                       SIM08320
      GOTO 2117                                                         SIM08330
C                                                   TEST U
 2116 IF(OS(1).NE.OS(2)) GOTO 230                                       SIM08350
 2117 ALTBLO=OS(3)                                                      SIM08360
      IF(ALTBLO.EQ.0) GOTO 4002                                         SIM08370
      NEXBLO=ALTBLO                                                     SIM08380
      GOTO 231                                                          SIM08390
C                                                   TABULATE
 212  IF(OS(2).GT.NTAB) CALL ERRORZ(435,0,&9999)                        SIM08410
      RARG=OS(1)                                                        SIM08420
      IF(INTDEC(1).EQ.1) RARG=FOS(1)                                    SIM08430
      TBLNO=OS(2)                                                       SIM08440
      WTFAC=OS(3)                                                       SIM08450
      IF(INTDEC(3).EQ.1) WTFAC=FOS(3)                                   SIM08460
      IF(WTFAC.EQ.0) WTFAC=1                                            SIM08470
      N=X(TAB+TBLNO)                                                    SIM08480
      RX(N+1)=RX(N+1)+RARG                                              SIM08490
      RX(N+2)=RX(N+2)+(RARG**2)                                         SIM08500
      RX(N+3)=RX(N+3)+(RARG*WTFAC)                                      SIM08510
      RX(N+4)=RX(N+4)+(RARG**2)*WTFAC                                   SIM08520
      X(N+5)=X(N+5)+WTFAC                                               SIM08530
      FREWDT=X(N+6)                                                     SIM08540
```

```
      MRNG=X(N+8)                                                       SIM08550
      ULLI=X(N+9)                                                       SIM08560
      PNTF=N+9                                                          SIM08570
      J=(RARG-ULLI)/FREWDT+2.                                           SIM08580
      IF (J.LT.1) J=1                                                   SIM08590
      IF(J.GT.MRNG) J=MRNG                                              SIM08600
 2122 X(PNTF+J)=X(PNTF+J)+WTFAC                                         SIM08610
      IF (J.EQ.MRNG) RX(N+7)=RX(N+7)+RARG                               SIM08620
      GOTO 230                                                          SIM08630
C                                                 SAVEVALUE
 213  IF(OS(1).GT.NSAV) CALL ERRORZ(433,0,&9999)                        SIM08650
      IF(MDFR-2) 2131,2132,2133                                         SIM08660
 2131 X(SAVE+OS(1))=X(SAVE+OS(1))-OS(2)                                 SIM08670
      GOTO 230                                                          SIM08680
 2132 X(SAVE+OS(1))=OS(2)                                               SIM08690
      GOTO 230                                                          SIM08700
 2133 X(SAVE+OS(1))=X(SAVE+OS(1))+OS(2)                                 SIM08710
      GOTO 230                                                          SIM08720
C                                                 GATE
 216  GOTO (217,218,219,220),MDFR                                       SIM08740
C                                                 GATE SNE
 217  CSTO=X(STO+OS(1))                                                 SIM08760
      ALTBLO=OS(2)                                                      SIM08770
      USED=X(CSTO+1)                                                    SIM08780
      IF(USED.NE.0) GOTO 230                                            SIM08790
      IF(ALTBLO.EQ.0) GOTO 2171                                         SIM08800
      NEXBLO=ALTBLO                                                     SIM08810
      GOTO 231                                                          SIM08820
 2171 FW1=X(CSTO+8)                                                     SIM08830
      FW2=X(CTRA+1)                                                     SIM08840
      HW3=HW2                                                           SIM08850
      HW2=CTRA                                                          SIM08860
 2172 X(CSTO+8)=FW1                                                     SIM08870
      X(CTRA+1)=FW2                                                     SIM08880
      FW1=X(CTRA+6)                                                     SIM08890
      BYTE(2)=.FALSE.                                                   SIM08900
      X(CTRA+6)=FW1                                                     SIM08910
      GOTO 4002                                                         SIM08920
C                                                 GATE SF
 218  CSTO=X(STO+OS(1))                                                 SIM08940
      ALTBLO=OS(2)                                                      SIM08950
      AVAIL=X(CSTO+2)                                                   SIM08960
      IF(AVAIL.EQ.0) GOTO 230                                           SIM08970
      IF(ALTBLO.EQ.0) GOTO 2181                                         SIM08980
      NEXBLO=ALTBLO                                                     SIM08990
      GOTO 231                                                          SIM09000
 2181 FW1=X(CSTO+8)                                                     SIM09010
      FW2=X(CTRA+1)                                                     SIM09020
```

```
      HW3=HW1                                                           SIM09030
      HW1=CTRA                                                          SIM09040
      GOTO 2172                                                         SIM09050
C                                      GATE SNF
 219  CSTO=X(STO+OS(1))                                                 SIM09070
      ALTBLO=OS(2)                                                      SIM09080
      AVAIL=X(CSTO+2)                                                   SIM09090
      IF(AVAIL.NE.0) GOTO 230                                           SIM09100
      IF(ALTBLO.EQ.0) GOTO 2191                                         SIM09110
      NEXBLO=ALTBLO                                                     SIM09120
      GOTO 231                                                          SIM09130
 2191 FW1=X(CSTO+9)                                                     SIM09140
      FW2=X(CTRA+1)                                                     SIM09150
      HW3=HW2                                                           SIM09160
      HW2=CTRA                                                          SIM09170
      GOTO 2172                                                         SIM09180
C                                      GATE SE
 220  CSTO=X(STO+OS(1))                                                 SIM09200
      ALTBLO=OS(2)                                                      SIM09210
      USED=X(CSTC+1)                                                    SIM09220
      IF(USED.EQ.0) GOTO 230                                            SIM09230
      IF(ALTBLO.EQ.0) GOTO 2201                                         SIM09240
      NEXBLO=ALTBLO                                                     SIM09250
      GOTO 231                                                          SIM09260
 2201 FW1=X(CSTO+9)                                                     SIM09270
      FW2=X(CTRA+1)                                                     SIM09280
      HW3=HW1                                                           SIM09290
      HW1=CTRA                                                          SIM09300
      GOTO 2172                                                         SIM09310
C                                      SELECT
 221  TPAR=OS(1)                                                        SIM09330
      LOW=OS(2)                                                         SIM09340
      HIGH=OS(3)                                                        SIM09350
      COMVAL=OS(4)                                                      SIM09360
      ALTBLO=OS(6)                                                      SIM09370
      IF(INTDEC(4).EQ.1) COMVAL=FOS(4)                                  SIM09380
      TRTN=ZRTN                                                         SIM09390
      ZRTN=2211                                                         SIM09400
      TEMP1=X(CBLO+1)                                                   SIM09410
      TEMP2=X(CBLO+2)                                                   SIM09420
      DO 2230 I=LOW,HIGH                                                SIM09430
      HW1=-33                                                           SIM09440
      HW2=0                                                             SIM09450
      X(CBLO+2)=FW1                                                     SIM09460
      FW1=X(CBLO+6)                                                     SIM09470
      HW2=I                                                             SIM09480
      X(CBLO+1)=FW1                                                     SIM09490
      INST=CBLO+1                                                       SIM09500
```

```
      GOTO 100                                                          SIM09510
 2211 J=0                                                               SIM09520
      GOTO (2213,2214,2215,2216,2217,2218,2219,2220,                    SIM09530
     -2221,2222,2223,2224),MDFR                                         SIM09540
2213  IF(COMVAL.EQ.OS(1)) GOTO 2231                                     SIM09550
      GOTO 2230                                                         SIM09560
2214  IF(COMVAL.LT.OS(1)) GOTO 2231                                     SIM09570
      GOTO 2230                                                         SIM09580
2215  IF(COMVAL.LE.OS(1)) GOTO 2231                                     SIM09590
      GOTO 2230                                                         SIM09600
2216  IF(COMVAL.GT.OS(1)) GOTO 2231                                     SIM09610
      GOTO 2230                                                         SIM09620
2217  IF(COMVAL.GE.OS(1)) GOTO 2231                                     SIM09630
      GOTO 2230                                                         SIM09640
2218  IF(COMVAL.NE.OS(1)) GOTO 2231                                     SIM09650
      GOTO 2230                                                         SIM09660
2219  IF(I.EQ.HIGH) GOTO 2231                                           SIM09670
      IF(J.GE.OS(1)) GOTO 2231                                          SIM09680
      J=OS(1)                                                           SIM09690
      K=I                                                               SIM09700
      GOTO 2230                                                         SIM09710
 2220 IF(I.EQ.HIGH) GOTO 2231                                           SIM09720
      IF(J.LE.OS(1)) GOTO 2231                                          SIM09730
      J=OS(1)                                                           SIM09740
      K=I                                                               SIM09750
      GOTO 2230                                                         SIM09760
 2221 IF(OS(1).GT.0) GOTO 2231                                          SIM09770
      GOTO 2230                                                         SIM09780
 2222 IF(OS(1).EQ.0) GOTO 2231                                          SIM09790
      GOTO 2230                                                         SIM09800
 2223 IF(OS(1).NE.0) GOTO 2231                                          SIM09810
      GOTO 2230                                                         SIM09820
 2224 IF(OS(1).EQ.0) GOTO 2231                                          SIM09830
      GOTO 2230                                                         SIM09840
 2230 CONTINUE                                                          SIM09850
 2231 X(CBLO+1)=TEMP1                                                   SIM09860
      X(CBLO+2)=TEMP2                                                   SIM09870
      X(CTRA+8+TPAR)=J                                                  SIM09880
      IF(ALTBLO.EQ.0) GOTO 230                                          SIM09890
      NEXBLO=ALTBLO                                                     SIM09900
      GOTO 231                                                          SIM09910
  229 CALL ERRORZ(603,11,&9999)                                         SIM09920
C                               RETURN FROM BLOCK ROUTINES
  230 FW1=X(CTRA+5)                                                     SIM09940
      FW2=X(CTRA+1)                                                     SIM09950
      JBL=HW4                                                           SIM09960
      HW4=HW1                                                           SIM09970
      HW1=HW1+1                                                         SIM09980
```

```
      GOTO 2311                                                         SIM09990
 231  FW1=X(CTRA+5)                                                     SIM10000
      FW2=X(CTRA+1)                                                     SIM10010
      JBL=HW4                                                           SIM10020
      HW4=HW1                                                           SIM10030
      HW1=NEXBLO                                                        SIM10040
 2311 X(CTRA+5)=FW1                                                     SIM10050
      X(CTRA+1)=FW2                                                     SIM10060
  232 N=X(BLOCK+JBL)                                                    SIM10070
      FW1=X(N+1)                                                        SIM10080
      IF(TRBLO) WRITE(OUT6,9040) HW1                                    SIM10090
      IF(HW1.EQ.1) GOTO 2313                                            SIM10100
 2312 IF(.NOT.TRBLO) GOTO 2315                                          SIM10110
      WRITE(OUT6,9031)                                                  SIM10120
      WRITE(OUT6,9032) CTRA,FTRA,FTCEC,LTCEC,FTFEC,LTFEC                SIM10130
 2315 IF(ZRTN.EQ.4005) GOTO 4005                                        SIM10140
      IF (ZRTN.EQ.2108) GO TO 2108                                      SIM10145
      CALL ERRORZ(603,12,&9999)                                         SIM10150
 2313 WRTN=ZRTN                                                         SIM10160
      TTRA=CTRA                                                         SIM10170
      TBLO=CBLO                                                         SIM10180
      ZRTN=2316                                                         SIM10190
      INST=N+2                                                          SIM10200
      GOTO 100                                                          SIM10210
 2316 OPCODE=1                                                          SIM10220
      CBLO=X(BLOCK+JBL)                                                 SIM10230
      ZRTN=2314                                                         SIM10240
      GOTO 200                                                          SIM10250
 2314 CTRA=TTRA                                                         SIM10260
      CBLO=TBLO                                                         SIM10270
      ZRTN=WRTN                                                         SIM10280
      GOTO 2312                                                         SIM10290
 299  CALL ERRORZ(2,0,&9999)                                            SIM10300
C
C                                           *** UPDATE CLOCK MOVE TRANS
C                                               FROM FEC TO CEC ***
 300  IF(FTFEC.EQ.0) CALL ERRORZ(401,0,&9999)                           SIM10330
      CLOCK=X(FTFEC+3)                                                  SIM10340
      IF(TRUPD) WRITE(OUT6,9023) CLOCK                                  SIM10350
 3001 IF(NOUPD.EQ.1) GOTO 3002                                          SIM10360
      CKPNT= 1                                                          SIM10370
      IF(TRS1) WRITE(OUT6,9042)                                         SIM10380
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM10390
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM10400
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM10410
      CTRA=FTFEC                                                        SIM10420
      FW1=X(CTRA+1)                                                     SIM10430
      FTFEC=HW2                                                         SIM10440
```

```
      IF(FTFEC.EQ.0) GOTO 3002                                          SIM10450
      FW1=X(FTFEC+1)                                                    SIM10460
      HW1=0                                                             SIM10470
      X(FTFEC+1)=FW1                                                    SIM10480
 3002 X(CTRA+1)=X(CTRA+2)                                               SIM10490
      CKPNT= 2                                                          SIM10500
      IF(TRS1) WRITE(OUT6,9042)                                         SIM10510
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM10520
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM10530
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM10540
      IF(FTCEC.LE.0) GOTO 3003                                          SIM10550
      FW1=X(CTRA+5)                                                     SIM10560
      NEWPRI=HW2                                                        SIM10570
      HW2=FTCEC                                                         SIM10580
      GOTO 3004                                                         SIM10590
 3003 FTCEC=CTRA                                                        SIM10600
      CKPNT= 3                                                          SIM10610
      IF(TRS1) WRITE(OUT6,9042)                                         SIM10620
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM10630
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM10640
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM10650
      LTCEC=FTCEC                                                       SIM10660
      X(CTRA+2)=0                                                       SIM10670
      GOTO 3005                                                         SIM10680
 3004 PNTT=HW2                                                          SIM10690
      CKPNT= 4                                                          SIM10700
      IF(TRS1) WRITE(OUT6,9042)                                         SIM10710
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM10720
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM10730
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM10740
      FW2=X(PNTT+5)                                                     SIM10750
      OLDPRI=HW4                                                        SIM10760
      FW1=X(PNTT+2)                                                     SIM10770
      IF(HW2.EQ.0) GOTO 3006                                            SIM10780
      IF(NEWPRI.LE.OLDPRI) GOTO 3004                                    SIM10790
      FW2=X(CTRA+2)                                                     SIM10800
      HW4=HW2                                                           SIM10810
      HW3=PNTT                                                          SIM10820
      X(CTRA+2)=FW2                                                     SIM10830
      FW2=X(HW2+2)                                                      SIM10840
      HW3=CTRA                                                          SIM10850
      X(HW2+2)=FW2                                                      SIM10860
      HW2=CTRA                                                          SIM10870
      X(PNTT+2)=FW1                                                     SIM10880
      IF(TRUPD) WRITE(OUT6,9033)                                        SIM10890
      IF(TRUPD) WRITE(OUT6,9032) PNTT,CTRA,FTCEC,LTCEC,FTFEC,LTFEC      SIM10900
 3005 IF(NOUPD.EQ.1) GOTO 2014                                          SIM10910
      IF(FTFEC.LE.0) GOTO 400                                           SIM10920
```

```
      CKPNT= 5                                                          SIM10930
      IF(TRS1) WRITE(OUT6,9042)                                         SIM10940
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM10950
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM10960
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM10970
      NEXBDT=X(FTFEC+3)                                                 SIM10980
      IF(NEXBDT.GT.CLOCK) GOTO 400                                      SIM10990
      GOTO 3001                                                         SIM11000
 3006 IF(NEWPRI.GT.OLDPRI) GOTO 3007                                    SIM11010
      CKPNT= 6                                                          SIM11020
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11030
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11040
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11050
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM11060
      FW2=X(PNTT+2)                                                     SIM11070
      HW4=CTRA                                                          SIM11080
      X(PNTT+2)=FW2                                                     SIM11090
      FW2=X(CTRA+2)                                                     SIM11100
      HW3=PNTT                                                          SIM11110
      HW4=0                                                             SIM11120
      X(CTRA+2)=FW2                                                     SIM11130
      LTCEC=CTRA                                                        SIM11140
      IF(NOUPD.EQ.1) GOTO 2014                                          SIM11150
      GOTO 3005                                                         SIM11160
 3007 FW2=X(CTRA+2)                                                     SIM11170
      CKPNT= 7                                                          SIM11180
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11190
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11200
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11210
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM11220
      HW3=HW1                                                           SIM11230
      HW4=PNTT                                                          SIM11240
      X(CTRA+2)=FW2                                                     SIM11250
      HW1=CTRA                                                          SIM11260
      X(PNTT+2)=FW1                                                     SIM11270
      IF(NOUPD.EQ.1) GOTO 2014                                          SIM11280
      GOTO 3005                                                         SIM11290
C
C                                       *** UNLINK FROM CEC AND
                                            MERGE INTO FEC ***
 310  FW1=X(CTRA+2)                                                     SIM11320
      TCTRA=HW2                                                         SIM11330
      CKPNT= 8                                                          SIM11340
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11350
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11360
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11370
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM11380
      IF(HW1.EQ.0) GOTO 3101                                            SIM11390
```

```
      FW2=X(HW1+2)                                                      SIM11400
      HW4=HW2                                                           SIM11410
      X(HW1+2)=FW2                                                      SIM11420
      GOTO 3102                                                         SIM11430
 3101 FTCEC=HW2                                                         SIM11440
      CKPNT= 9                                                          SIM11450
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11460
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11470
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11480
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM11490
 3102 IF(HW2.EQ.0) GOTO 3103                                            SIM11500
      CKPNT=10                                                          SIM11510
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11520
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11530
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11540
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM11550
      FW2=X(HW2+2)                                                      SIM11560
      HW3=HW1                                                           SIM11570
      X(HW2+2)=FW2                                                      SIM11580
      GOTO 3104                                                         SIM11590
 3103 LTCEC=HW1                                                         SIM11600
      CKPNT=11                                                          SIM11610
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11620
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11630
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11640
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM11650
C                                   UNLINKED
 3104 X(CTRA+2)=X(CTRA+1)                                               SIM11670
      CKPNT=12                                                          SIM11680
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11690
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11700
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11710
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM11720
      IF(FTFEC.EQ.0) GOTO 3108                                          SIM11730
      NEWBDT=X(CTRA+3)                                                  SIM11740
      HW2=FTFEC                                                         SIM11750
 3105 PNTT=HW2                                                          SIM11760
      CKPNT=13                                                          SIM11770
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11780
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11790
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11800
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM11810
      OLDBDT=X(PNTT+3)                                                  SIM11820
      FW1=X(PNTT+1)                                                     SIM11830
      IF(HW2.LE.0) GOTO 3107                                            SIM11840
      IF(NEWBDT.GE.OLDBDT) GOTO 3105                                    SIM11850
      IF(HW1.EQ.0) FTFEC=CTRA                                           SIM11860
      HW3=HW1                                                           SIM11870
```

```
      HW4=PNTT                                                          SIM11880
      X(CTRA+1)=FW2                                                     SIM11890
      IF(HW3.EQ.0) GOTO 3111                                            SIM11900
      FW3=X(HW3+1)                                                      SIM11910
      HW6=CTRA                                                          SIM11920
      X(HW3+1)=FW3                                                      SIM11930
      GOTO 3112                                                         SIM11940
 3106 HW4=PNTT                                                          SIM11950
      CKPNT=14                                                          SIM11960
      IF(TRS1) WRITE(OUT6,9042)                                         SIM11970
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM11980
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM11990
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM12000
      HW3=HW1                                                           SIM12010
      X(CTRA+1)=FW2                                                     SIM12020
      IF(HW1.EQ.0) GOTO 3111                                            SIM12030
 3110 FW2=X(HW1+1)                                                      SIM12040
      CKPNT=15                                                          SIM12050
      IF(TRS1) WRITE(OUT6,9042)                                         SIM12060
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM12070
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM12080
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM12090
      HW4=CTRA                                                          SIM12100
      X(HW1+1)=FW2                                                      SIM12110
      GOTO 3112                                                         SIM12120
 3111 FTFEC=CTRA                                                        SIM12130
      CKPNT=16                                                          SIM12140
      IF(TRS1) WRITE(OUT6,9042)                                         SIM12150
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM12160
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM12170
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM12180
 3112 HW1=CTRA                                                          SIM12190
      CKPNT=17                                                          SIM12200
      IF(TRS1) WRITE(OUT6,9042)                                         SIM12210
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM12220
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM12230
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM12240
      X(PNTT+1)=FW1                                                     SIM12250
      GOTO 3109                                                         SIM12260
 3107 IF(NEWBDT.LT.OLDBDT) GOTO 3106                                    SIM12270
      CKPNT=18                                                          SIM12280
      IF(TRS1) WRITE(OUT6,9042)                                         SIM12290
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM12300
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM12310
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM12320
      LTFEC=CTRA                                                        SIM12330
      HW4=0                                                             SIM12340
      HW3=PNTT                                                          SIM12350
```

```
      X(CTRA+1)=FW2                                                     SIM12360
      HW2=CTRA                                                          SIM12370
      X(PNTT+1)=FW1                                                     SIM12380
      GOTO 3109                                                         SIM12390
 3108 FTFEC=CTRA                                                        SIM12400
      CKPNT=19                                                          SIM12410
      IF(TRS1) WRITE(OUT6,9042)                                         SIM12420
      IF(TRS1) WRITE(OUT6,9043) CKPNT,FTFEC,LTFEC,FTCEC,LTCEC,          SIM12430
     -CTRA,PNTT,FTRA,X(CTRA+1),X(CTRA+2),X(CTRA+3),X(PNTT+1),X(PNTT+2), SIM12440
     -X(PNTT+3),NEWBDT,OLDBDT                                           SIM12450
      LTFEC=FTFEC                                                       SIM12460
      X(CTRA+1)=0                                                       SIM12470
 3109 IF(ZRTN.EQ.30) GOTO 30                                            SIM12480
      IF(ZRTN.EQ.2314) GOTO 2314                                        SIM12490
      CTRA=TCTRA                                                        SIM12500
      IF(TCTRA.EQ.0) GOTO 400                                           SIM12510
      IF(ZRTN.EQ.400 ) GOTO 400                                         SIM12520
      CALL ERRORZ(603,13,&9999)                                         SIM12530
C                                    *** SCAN ***
 400  IF(TRSCN) WRITE(OUT6,9024)                                        SIM12550
      SCFLAG=0                                                          SIM12560
 4001 CTRA=FTCEC                                                        SIM12570
      IF(CTRA.EQ.0) GOTO 300                                            SIM12580
 4008 FW1=X(CTRA+6)                                                     SIM12590
      SSIND=BYTE(2)                                                     SIM12600
      IF(SSIND) GOTO 4003                                               SIM12610
 4002 IF (SCFLAG.EQ.1) GO TO 400
      FW1=X(CTRA+2)                                                     SIM12620
      IF(HW2.EQ.0) GOTO 300                                             SIM12630
      CTRA=HW2                                                          SIM12640
      GOTO 4008                                                         SIM12650
 4003 FW1=X(CTRA+5)                                                     SIM12660
      CBLO=X(BLOCK+HW1)                                                 SIM12670
      INST=CBLO+2                                                       SIM12680
      FW1=X(CBLO+1)                                                     SIM12690
      OPCODE=HW1                                                        SIM12700
      ZRTN=4004                                                         SIM12710
      GOTO 100                                                          SIM12720
 4004 ZRTN=4005                                                         SIM12730
      GOTO 200                                                          SIM12740
 4005 FW1=X(CBLO+1)                                                     SIM12750
      OPCODE=HW1                                                        SIM12760
      IF(TRSCN) WRITE(OUT6,9034)                                        SIM12770
      IF(TRSCN) WRITE(OUT6,9035) SCFLAG,CBLO,OPCODE,INST                SIM12780
 4006 IF(OPCODE.NE.2) GOTO 4003                                         SIM12800
      NEWBDT=X(CTRA+3)                                                  SIM12810
      IF(NEWBDT.LE.CLOCK) GOTO 4003                                     SIM12820
```

```
      IF(TRSCN) WRITE(OUT6,9030) NEWBDT                                 SIM12830
      ZRTN=400                                                          SIM12840
      GOTO 310                                                          SIM12850
C                                                                       SIM12860
C                                                                       SIM12870
C                                                                       SIM12880
C                                          *** UPDATE FINAL INTERVAL ***
 9999 IF (ERR.NE.0) GO TO 5900                                          SIM12900
      IF (NSTO.EQ.0) GO TO 5200                                         SIM12910
      DO 5150 I=1,NSTO                                                  SIM12920
      N=X(STO+I)                                                        SIM12930
      IF (N.EQ.0.OR.X(N+6).EQ.0) GO TO 5150                             SIM12940
      DTIME=CLOCK-X(N+5)                                                SIM12950
      X(N+5)=CLOCK                                                      SIM12960
      FW1=X(N+3)                                                        SIM12970
      FW2=X(N+4)                                                        SIM12980
      DW1=DW1+DTIME*X(N+1)                                              SIM12990
      X(N+3)=FW1                                                        SIM13000
      X(N+4)=FW2                                                        SIM13010
 5150 CONTINUE                                                          SIM13020
 5200 IF (NQUE.EQ.0) GO TO 5300                                         SIM13030
      DO 5250 I=1,NQUE                                                  SIM13040
      N=X(QUE+I)                                                        SIM13050
      IF (N.EQ.0.OR.X(N+2).EQ.0) GO TO 5250                             SIM13060
      DTIME=CLOCK-X(N+1)                                                SIM13070
      X(N+1)=CLOCK                                                      SIM13080
      FW1=X(N+4)                                                        SIM13090
      FW2=X(N+5)                                                        SIM13100
      DW1=DW1+DTIME*X(N+6)                                              SIM13110
      X(N+4)=FW1                                                        SIM13120
      X(N+5)=FW2                                                        SIM13130
 5250 CONTINUE                                                          SIM13140
 5300 CLOCKR=CLOCK-CLOCKB                                               SIM13150
      WRITE (OUT6,9550) CLOCKR,CLOCK                                    SIM13160
      GO TO 5910                                                        SIM13170
 5900 WRITE (OUT6,9026)                                                 SIM13180
 5910 IF (OUTX.EQ.0) RETURN                                             SIM13190
      WRITE (OUTX,9020)                                                 SIM13200
      WRITE (OUTX,9018)                                                 SIM13210
      DO 5930 I=1,TRSIZE                                                SIM13220
      FW1=X(I)                                                          SIM13230
      IF (HW1.GE.16000.OR.HW1.LT.-16000) GO TO 5920                     SIM13240
      WRITE (OUTX,9019) I,FW1,HW1,HW2                                   SIM13250
      GO TO 5930                                                        SIM13260
 5920 WRITE (OUTX,9027) I,FW1,HW1,HW2,FFW1                              SIM13270
 5930 CONTINUE                                                          SIM13280
      RETURN                                                            SIM13285
```

```
C                                         ***** SPSTAT *****
      ENTRY SPSTAT(SNA,IDT,VAL,IORD)                                    SIM13320
      INTEGER*2 SNA,IDT,IORD                                            SIM13330
      HW1=SNA                                                           SIM13340
      HW2=IDT                                                           SIM13350
      VAL=0                                                             SIM13360
      IF (CLOCK.EQ.0) RETURN                                            SIM13365
      RVAL=0.                                                           SIM13370
      EPT=2                                                             SIM13380
      IF (SNA.GE.5.AND.SNA.LE.21.OR.SNA.GE.27.AND.SNA.LE.29) GO TO 1006 SIM13390
      WRITE (6,9521)                                                    SIM13400
      RETURN                                                            SIM13410
C                                                                       SIM13420
 5950 IF (RVAL.EQ.0.) GO TO 5952                                        SIM13430
      IORD=1                                                            SIM13440
      FFW1=RVAL                                                         SIM13450
      GO TO 5954                                                        SIM13470
 5952 IORD=0                                                            SIM13480
 5954 VAL=FW1                                                           SIM13500
      RETURN                                                            SIM13510

C                                         ***** SIMOUT *****
      ENTRY SIMOUT(OUT6)                                                SIM13550
      INTEGER*2 I2,HC1 /1/,HC55 /55/,HC2 /2/,HC3 /3/                    SIM13560
      REAL*8 STATSW(4),BITTS                                            SIM13570
C                                         OUTPUT STORAGE STATISTICS
      CALL GBITS(HC1,HC55,STATSW(1),BITTS)                              SIM13580
      IF (NSTO.EQ.0.OR.BITTS.EQ.0.) GO TO 6100                          SIM13590
      WRITE (OUT6,9500)                                                 SIM13600
      DO 6050 I2=1,NSTO                                                 SIM13610
      CALL GBITS(I2,I2,STATSW(1),BITTS)                                 SIM13620
      N=X(STO+I2)                                                       SIM13630
      IF (N.EQ.0.OR.BITTS.EQ.0.) GO TO 6050                             SIM13640
      FW1=X(N+3)                                                        SIM13650
      FW2=X(N+4)                                                        SIM13660
      FW3=X(N+1)+X(N+2)                                                 SIM13670
      RR1=DW1/CLOCK                                                     SIM13680
      RR2=DW1/(CLOCK*FW3)                                               SIM13690
      RR3=0.                                                            SIM13700
```

```
      IF (X(N+6).NE.0) RR3=DW1/X(N+6)                                   SIM13710
      WRITE (OUT6,9101) I2,FW3,RR1,RR2,X(N+6),RR3,X(N+1),X(N+7)         SIM13720
 6050 CONTINUE                                                          SIM13730
C                                   OUTPUT QUEUE STATISTICS
 6100 CALL GBITS(HC1,HC55,STATSW(2),BITTS)                              SIM13740
      IF (NQUE.EQ.0.OR.BITTS.EQ.0.) GO TO 6200                          SIM13750
      WRITE (OUT6,9501)                                                 SIM13760
      DO 6150 I2=1,NQUE                                                 SIM13770
      CALL GBITS(I2,I2,STATSW(2),BITTS)                                 SIM13780
      N=X(QUE+I2)                                                       SIM13790
      IF (N.EQ.0.OR.BITTS.EQ.0.) GO TO 6150                             SIM13800
      FW1=X(N+4)                                                        SIM13810
      FW2=X(N+5)                                                        SIM13820
      RR1=DW1/CLOCK                                                     SIM13830
      RR2=0.                                                            SIM13840
      IF (X(N+2).NE.0) RR2=100.*X(N+3)/X(N+2)                           SIM13850
      RR3=0.                                                            SIM13860
      IF (X(N+2).NE.0) RR3=DW1/X(N+2)                                   SIM13870
      RR4=0.                                                            SIM13875
      IF (X(N+2).NE.X(N+3)) RR4=DW1/(X(N+2)-X(N+3))                     SIM13880
      WRITE (OUT6,9103) I2,X(N+7),RR1,X(N+2),X(N+3),RR2,RR3,RR4,X(N+6)  SIM13890
 6150 CONTINUE                                                          SIM13900
      WRITE (OUT6,9502)                                                 SIM13910
C                                   OUTPUT TABLE STATISTICS
 6200 CALL GBITS(HC1,HC55,STATSW(3),BITTS)                              SIM13920
      IF (NTAB.EQ.0.OR.BITTS.EQ.0.) GO TO 6300                          SIM13930
      DO 6250 I2=1,NTAB                                                 SIM13940
      CALL GBITS(I2,I2,STATSW(3),BITTS)                                 SIM13950
      N=X(TAB+I2)                                                       SIM13960
      IF (N.EQ.0.OR.BITTS.EQ.0.) GO TO 6250                             SIM13970
      IF (X(N+5).GT.1) GO TO 6210                                       SIM13980
      RR1=RX(N+1)                                                       SIM13990
      RR2=0.                                                            SIM14000
      GO TO 6220                                                        SIM14010
 6210 RR1=RX(N+1)/X(N+5)                                                SIM14020
      RR2=SQRT((RX(N+2)-RX(N+1)**2/X(N+5))/(X(N+5)-1))                  SIM14030
 6220 WRITE (OUT6,9503) I2,X(N+5),RR1,RR2,RX(N+1)                       SIM14040
      IF (X(N+5).EQ.0) GO TO 6245                                       SIM14050
      FRNG=X(N+8)                                                       SIM14060
      RR4=0.                                                            SIM14070
      DO 6240 J=1,FRNG                                                  SIM14080
      FW1=X(N+9+J)                                                      SIM14090
      RR3=100.*FW1/X(N+5)                                               SIM14100
      RR4=RR4+RR3                                                       SIM14110
      RR5=100.-RR4                                                      SIM14120
      FW2=X(N+9)+(J-1)*X(N+6)                                           SIM14130
      IF (RR1.EQ.0.) GO TO 6225                                         SIM14140
      RR6=FW2/RR1                                                       SIM14150
```

```
      GO TO 6228                                                        SIM14160
 6225 RR6=0.                                                            SIM14170
 6228 IF (RR2.EQ.0.) GO TO 6230                                         SIM14180
      RR7=(FW2-RR1)/RR2                                                 SIM14190
      GO TO 6232                                                        SIM14200
 6230 RR7=0.                                                            SIM14210
 6232 IF (J.EQ.FRNG) GO TO 6235                                         SIM14220
      WRITE(OUT6,9110) FW2,FW1,RR3,RR4,RR5,RR6,RR7                      SIM14230
      GO TO 6240                                                        SIM14240
 6235 IF (FW1.EQ.0) GO TO 6245                                          SIM14250
      FFW3=RX(N+7)/FW1                                                  SIM14260
      WRITE(OUT6,9509) FW1,RR3,RR4,RR5,FFW3                             SIM14270
 6240 CONTINUE                                                          SIM14280
      GO TO 6250                                                        SIM14290
 6245 WRITE(OUT6,9510)                                                  SIM14300
 6250 CONTINUE                                                          SIM14310
C                                          OUTPUT SAVEVALUES
 6300 CALL GBITS(HC1,HC1,STATSW(4),BITTS)                               SIM14320
      IF (NSAV.EQ.0.OR.BITTS.EQ.0.) GO TO 6400                          SIM14330
      WRITE(OUT6,9504)                                                  SIM14340
      DO 6350, I=1,NSAV                                                 SIM14350
      IF (X(SAVE+I).NE.0) WRITE(OUT6,9112) I,X(SAVE+I)                  SIM14360
 6350 CONTINUE                                                          SIM14370
C                                          OUTPUT CEC AND FEC
 6400 FLAG=0                                                            SIM14380
      CALL GBITS(HC2,HC2,STATSW(4),BITTS)                               SIM14390
      IF (BITTS.EQ.0.) GO TO 6500                                       SIM14400
      N=FTCEC                                                           SIM14410
      WRITE(OUT6,9505)                                                  SIM14420
      WRITE(OUT6,9506)                                                  SIM14430
 6420 IF (N.EQ.0) GO TO 6500                                            SIM14440
      FW1=X(N+6)                                                        SIM14450
      FW2=X(N+8)                                                        SIM14460
      FW3=X(N+1)                                                        SIM14470
      IF (FLAG.EQ.1) FW3=X(N+2)                                         SIM14480
      FW4=X(N+5)                                                        SIM14490
      HW4=(N-TRAN)/(NPAR+8)+1                                           SIM14500
      WRITE(OUT6,9115) HW4,X(N+3),HW6,HW7,X(N+4),(X(N+8+J),J=1,4),      SIM14510
     -BYTE(2),BYTE(1)                                                   SIM14520
      IF (NPAR.GT.4) WRITE(OUT6,9116) (X(N+8+J),J=5,NPAR)               SIM14530
      FW1=X(N+2-FLAG)                                                   SIM14540
      N=HW2                                                             SIM14550
      GO TO 6420                                                        SIM14560
 6500 IF (FLAG.NE.0) GO TO 6600                                         SIM14570
      CALL GBITS(HC3,HC3,STATSW(4),BITTS)                               SIM14580
      IF (BITTS.EQ.0.) GO TO 6600                                       SIM14590
      FLAG=1                                                            SIM14600
      N=FTFEC                                                           SIM14610
```

```
      WRITE(OUT6,9507)                                                  SIM14620
      WRITE(OUT6,9506)                                                  SIM14630
      GO TO 6420                                                        SIM14640
C                                       ZERO OUTPUT STATISTIC
C                                       SWITCHES AND RETURN
 6600 DO 6650 I=1,4                                                     SIM14650
      STATSW(I)=0.                                                      SIM14660
 6650 CONTINUE                                                          SIM14670
      WRITE (OUT6,9551)
      RETURN                                                            SIM14680



C                                       ***** SETIND *****

      ENTRY SETIND(ROW,FB)                                              SIM14720
      REAL*8 DONES /ZFFFFFFFFFFFFFFFF/                                  SIM14730
      INTEGER*2 FB,LB,ROW                                               SIM14740
C                                       SET OUTPUT STATISTIC
C                                       SWITCHES AND RETURN
      IF (FB.LE.0) FB=60                                                SIM14745
      IF (ROW.LT.1.OR.ROW.GT.6) ROW=6                                   SIM14750
      IF (ROW.NE.6) GO TO 7100                                          SIM14760
      DO 7050 I=1,4                                                     SIM14770
 7050 STATSW(I)=DONES                                                   SIM14780
      RETURN                                                            SIM14790
 7100 I2=ROW                                                            SIM14800
      IF (I2.EQ.5) I2=1                                                 SIM14810
      LB=FB                                                             SIM14820
      IF (FB.LE.55) GO TO 7130                                          SIM14830
      FB=1                                                              SIM14840
      LB=55                                                             SIM14850
 7130 CALL PBITS(FB,LB,STATSW(I2),DONES)                                SIM14860
      IF (ROW.EQ.5) CALL PBITS(FB,LB,STATSW(2),DONES)                   SIM14870
      RETURN                                                            SIM14880

C****************************************** FORMATS ********************************

 9002 FORMAT(' SLCPE COMPUTATION')                                      SIM14940
 9003 FORMAT(' BEGIN NEW SIMULATION')                                   SIM14950
 9004 FORMAT(' CLEAR-CONTINUE SIMULATION')                              SIM14960
 9005 FORMAT(' RESET-CONTINUE SIMULATION')                              SIM14970
 9006 FORMAT(' EVALUATE ARGUMENTS')                                     SIM14980
 9007 FORMAT(' PERFORM BLCCK ROUTINE',2X,'OPCODE=',I2,2X,'CBLO=', I5)   SIM14990
 9015 FORMAT(I4,I4,I3,7I8)                                              SIM15000
 9016 FORMAT(' ARG',I2,' = ',F15.5)                                     SIM15010
 9018 FORMAT( 9X,'HEX',8X,'DEC',6X,'DEC')                               SIM15020
```

```
9019 FORMAT(' ',I3,4X,Z8,3X,I6,3X,I6)
9020 FORMAT('1',8X,'FW1',8X,'HW1',6X,'HW2')
9021 FORMAT(' CREATE = ',I6)
9023 FORMAT(' UPDATE CLOCK, TIME=',I10)
9024 FORMAT(' SCAN')
9025 FORMAT(' ENTER OPTIONAL DATA FOR SIMULATION ROUTINE')
9026 FORMAT(' ABNORMAL TERMINATION')
9027 FORMAT(' ',I3,4X,Z8,3X,I6,3X,I6,3X,1E12.6)
9030 FORMAT(' NEWBDT=',I10)
9031 FORMAT('   CTRA  FTRA FTCEC LTCEC FTFEC LTFEC')
9032 FORMAT(' ',6I6)
9033 FORMAT('   PNTT  CTRA FTCEC LTCEC FTFEC LTFEC')
9034 FORMAT(' SCFLAG  CBLO OPCODE  INST')
9035 FORMAT(2I6,I7,I6)
9036 FORMAT(' FTRA=',I6)
9038 FORMAT(' OPCODE=',I3)
9040 FORMAT(' LAST BLOCK OPCODE=',I4)
9041 FORMAT(' TRANSACTION IN TERMINATE BLOCK     TERMINATIONS TO GO=',
    -I10)
9042 FORMAT('  CKPNT FTFEC LTFEC FTCEC LTCEC  CTRA  PNTT',
    -'  FTRA   X(C+1)   X(C+2)   X(C+3)   X(P+1)   X(P+2)   X(P+3)
    - NBDT    OBDT')
9043 FORMAT(' ',8I6,2X,Z8,1X,Z8,1I9,1X,Z8,1X,Z8,3I9)
9101 FORMAT (' ',I5,7X,I5,8X,F7.3,8X,F5.3,8X,I5,7X,F9.3,5X,I5,7X,I5)
9103 FORMAT (' ',I4,5X,I5,6X,F7.3,4X,I5,6X,I5,6X,F7.3,4X,F9.3,4X,
    1F9.3,4X,I5)
9110 FORMAT (' ',5X,I5,5X,I7,7X,F7.2,6X,F8.2,7X,F8.2,7X,F8.3,5X,F9.3)
9112 FORMAT (' ',10X,I4,2X,I12)
9115 FORMAT (' ',I5,1X,I7,5X,I4,3X,I4,4X,I9,4(1X,I8),2(4X,L2))
9116 FORMAT (' ',42X,24(4(1X,I8),/,' ',42X))
9500 FORMAT (////,' ','STORAGE',5X,'CAPACITY',5X,'AVERAGE',7X,
    1'AVERAGE',7X,'ENTRIES',6X,'AVERAGE',6X,'CURRENT',5X,'MAXIMUM',
    2/,' ',24X,'CONTENTS',5X,'UTILIZATION',16X,'TIME/TRAN',5X,
    3'CONTENTS',4X,'CONTENTS',/)
9501 FORMAT (////,' ','QUEUE',4X,'MAXIMUM',4X,'AVERAGE',5X,'TOTAL',
    16X,'ZERO',6X,'PERCENT',5X,'AVERAGE',5X,'$AVERAGE',5X,'CURRENT',
    2/,' ',8X,'CONTENTS',3X,'CONTENTS',4X,'ENTRIES',3X,'ENTRIES',6X,
    3'ZEROS',4X,'TIME/TRANS',3X,'TIME/TRANS',3X,'CONTENTS',/)
9502 FORMAT (/,' ','$AVERAGE TIME/TRANS = AVERAGE TIME/TRANS EXCLUDING
    1ZERO ENTRIES')
9503 FORMAT(////,' ','TABLE',I5,//,' ','ENTRIES IN TABLE',10X,'MEAN ARG
    1UMENT',10X,'STANDARD DEVIATION',10X,'SUM OF ARGUMENTS',/,' ',I10,1
    26X,F11.3,11X,F14.3,14X,F13.3,//,' ',5X,'UPPER',5X,'OBSERVED',5X,'PS
    3ER CENT',5X,'CUMULATIVE',5X,'CUMULATIVE',5X,'MULTIPLE',5X,'DEVIATI
    4ON',/,' ',5X,'LIMIT',4X,'FREQUENCY',5X,'OF TOTAL',5X,'PERCENTAGE',
    56X,'REMAINDER',6X,'OF MEAN',5X,'FROM MEAN')
9504 FORMAT (////,' ','CONTENTS OF FULLWORD SAVEVALUES (NON-ZERO)',/,
    1' ','SAVEVALUE   NR,        VALUE',/)
```

```
9505 FORMAT (////,' ','CURRENT EVENTS CHAIN')                              SIM15510
9506 FORMAT (' ','TRANS',5X,'BDT',4X,'BLOCK',4X,'NBA',4X,'MARK-TIME',    SIM15520
    17X,'P1',7X,'P2',7X,'P3',7X,'P4',4X,'SI',4X,'TI',/)                  SIM15530
9507 FORMAT (////,' ','FUTURE EVENTS CHAIN')                               SIM15540
9508 FORMAT (' ','SIMULATION TERMINATED')                                  SIM15550
9509 FORMAT (' ',2X,'OVERFLOW',5X,I7,7X,F7.2,6X,F8.2,7X,F8.2,             SIM15560
    1       /, '    AVERAGE VALUE OF OVERFLOW',2X,F12.3)                  SIM15570
9510 FORMAT ( '    REMAINING FREQUENCIES ARE ALL ZERO')                    SIM15580
9521 FORMAT(' INVALID SNA PASSED TO SPSTAT')                               SIM15600
9550 FORMAT (' SIMULATION TIME IS ',I10,' (RELATIVE),',I10,               SIM15630
    1        ' (ABSOLUTE).')                                               SIM15640
9551 FORMAT (/////)
     END                                                                   SIM15650


100  SUBROUTINE ERRORZ(ERRNO,RECNO,*)                                      SIM15710
     COMMON /XVECTR/ MAXX,X                                                SIM15720
     INTEGER*4 ERRNO,RECNO,X(1000)                                         SIM15730
     X(30)=ERRNO                                                           SIM15740
     WRITE(6,1001) ERRNO,RECNO                                             SIM15750
1001 FORMAT('0ERRNO',2X,1I3,2X,'RECNO',2X,1I4)                            SIM15760
     RETURN 1                                                              SIM15770
     END                                                                   SIM15780
```

# APPENDIX D

## *** NLPQ RULE ADDITIONS AND MODIFICATIONS ***

```
NAMED RECORDS:
        SETMEM    (-GPSSSW(MEM),-XVSW(MEM))
        AVERAGE   (PS='ADJ')
        UTILIZA   (PS='NCUNS',INCOMP)
        TRANSIT   (PS='NOUNS')
        CONTENT   (PS='NCUNS')
        CURRENT   (PS='ADJ')
        MAXIMUM   (PS='ADJ')
        PRINT     (PS='VERBS',NSFX)
        STORAGE   ('GPSSENTY',PRCODE=1)
        QUEUE     ('GPSSENTY',PRCODE=2)
        TABLE     ('GPSSENTY',PRCODE=3)
        GPSSENTY  (PS='NOUNS')
        STATIST   (PS='NCUNS',INCOMP)
        GPSSATTR  ('ATTR')

        SC        ('GPSSATTR',SNACODE=5,CHARS="NUMBER OF ENTRIES")
        SM        ('GPSSATTR',SNACODE=6,CHARS="MAXIMUM CONTENTS")
        SR        ('GPSSATTR',SNACODE=7,CHARS="AVERAGE UTILIZATION")
        SA        ('GPSSATTR',SNACODE=8,CHARS="AVERAGE CONTENTS")
        S         ('GPSSATTR',SNACODE=9,CHARS="CURRENT CONTENTS")
        R         ('GPSSATTR',SNACODE=10,CHARS="REMAINING CONTENTS")
        ST        ('GPSSATTR',SNACODE=11,CHARS="AVERAGE SERVICE TIME")
        Q         ('GPSSATTR',SNACODE=12,CHARS="CURRENT LINE LENGTH")
        QA        ('GPSSATTR',SNACODE=13,CHARS="AVERAGE LINE LENGTH")
        QM        ('GPSSATTR',SNACODE=14,CHARS="MAXIMUM LINE LENGTH")
        QC        ('GPSSATTR',SNACODE=15,CHARS="NUMBER OF ENTRIES")
        QZ        ('GPSSATTR',SNACODE=16,CHARS="NUMBER OF ZERO ENTRIES")
        QT        ('GPSSATTR',SNACODE=17,CHARS="AVERAGE WAITING TIME")
        QX        ('GPSSATTR',SNACODE=18,
                   CHARS="AVERAGE WAITING TIME EXCLUDING ZERO ENTRIES")
        TB        ('GPSSATTR',SNACODE=19,CHARS="MEAN TRANSIT TIME")
        TC        ('GPSSATTR',SNACODE=20,CHARS="NUMBER OF ENTRIES")
        TD        ('GPSSATTR',SNACODE=21,CHARS="STANDARD DEVIATION")
        C         ('GPSSATTR',SNACODE=27,CHARS="CLOCK")
        X         ('GPSSATTR',SNACODE=28,CHARS="SAVEVALUE")
        QP        ('GPSSATTR',SNACODE=29,CHARS="PERCENT ZERO ENTRIES")

ROUTINES:
        SIMULT 21,   SIMOUT 22,   SETIND 23,   SPSTAT 24
```

```
DELETE XPARG E:
DELETE XCODE E:
DELETE XVECTOR E:

MORPHOLOGY FOR ENCODING X-VECTOR:

          XPARG($'ACTION')     -->      ...
               XVECTOR(RIGHT=IPDP(XPARG),LR('BACKSTUF')=LR('BACKSTUF')+1,
                      @LR('BACKSTUF')('BACKSTUF')=FX(MEM)+INDX(MEM),
                      LR('BACKSTUF')=LR('BACKSTUF')+1,
                      @LR('BACKSTUF')('BACKSTUF')=RIGHT)
          XPARG($'ENTITY')     -->     XVECTOR(RIGHT=IDNO(XPARG))
          XPARG('DECIMAL')     -->      ...
               NULL(IX=FX(MEM)+INDX(MEM),XV=NUM(XPARG),
                    PUTFPX,¬INDX(MEM),FX(MEM)=FX(MEM)+1)
          XPARG($'ABSTIME')     -->     TIMARG(%XPARG,XVSW)
          XPARG($'QUANVAL')     -->     XVECTOR(RIGHT=NUM(XPARG))
          XPARG('SNAREF',NUM)     -->      ...
               XCODE(RIGHT=NUM(XPARG),NAM(XPARG),LEFT=22,
                     NAM.NE."FN",-LEFT)
          XPARG('SNAREF')     -->      ...
               XCODE(RIGHT=IDNO(NAM2(XPARG)),NAM(XPARG),LEFT=12,
                     NAM.NE."Q",LEFT=13,NAM.NE."QA",-LEFT)
          XPARG('PARAMNO')     -->     XCODE(LEFT=1,RIGHT=NUM(XPARG))
          XPARG('TRANSTIM')     -->     XCODE(LEFT=3,RIGHT=1)
          XPARG('RANDM')     -->      ...
               XCODE(LEFT=26,XRNNC(MEM)=XRNNC(MEM)+1,RIGHT=XRNNO(MEM),
                     XRNNO(MEM).EQ.8,-XRNNC(MEM))
          XPARG('NORMAL')     -->     XCODE(LEFT=24,RIGHT=IDNO(XPARG))
          XPARG(MEAN,STDEV)     -->      ...
               XARG(DATA=MEAN(XPARG))     XARG(DATA=STDEV(XPARG))   ...
               XCODE(LEFT=22,RIGHT=2)   ...
               XCODE(LEFT=30,RIGHT=3)   ...
               XCODE(LEFT=30,RIGHT=1)   ...
               XCODE(LEFT=25,RIGHT=0)
          XPARG(XYLAST)     -->     XCODE(LEFT=22,RIGHT=IDNO(XPARG))

          XCODE     -->     XVECTOR(%XCODE,LEFT=0-LEFT)

          XVECTOR(INDX)     -->     XVECTOR(INDX(MEM)=INDX,-INDX)
          XVECTOR(¬IX)     -->
               XVECTOR(IX=FX(MEM)+INDX(MEM),
                      ¬INDX(MEM),TEMP=0-LEFT,TEMP.NE.33,TEMP.NE.25,
                      FX(MEM)=FX(MEM)+1)
          XVECTOR     -->
               NULL(%XVECTOR,XV=LEFT,PUTLX,XV=RIGHT,PUTRX)
```

```
DELETE QUEST2 E:
SEMOLOGY FOR ENCODING ANSWERS TO QUESTIONS:
          QUEST2(¬ATTRIB)   -->   ANSWR('YES')      ...
                   SENT(%QUEST2,-PRED,-SUCC)
          QUEST2(ATTRIB$'GPSSATTR')   -->
                   SENT(%QUEST2,@8=SNACODE(ATTRIB),@9=IDNO,SPSTAT,@ATTRIB=@9)
          QUEST2(¬@ATTRIB)   -->   ANSWR('IDK')
          QUEST2(¬VAL|VAL$'INTRGVAL')   -->   QUEST5(%QUEST2)
          QUEST2(@ATTRIB.NE.ENTY(VAL))   -->   ANSWR('NC')   QUEST5(%QUEST2)
          QUEST2(VALQUAN,¬QUANTITY)   -->   ANSWR('IDK')
          QUEST2(VALQUAN,VALQUAN.NE.QUANTITY)   -->      ...
                   ANSWR('NO')      ...
                   SENT(%QUEST2,ATTRIB='QUANTITY')
          QUEST2   -->   ANSWR('YES')   QUEST5(%QUEST2)

DELETE ENCODING E:
SEMOLOGY FOR ENCODING  -  THE LINKAGE FROM DECODING:
          ENCODING(ETYPE.EQ.'QUESTION')   -->   QUESTION(%ENCODING)
          ENCODING(ETYPE.EQ.'REPLYERR')   -->
                   PHRASE(CHARS=" THAT IS NOT A REASONABLE REPLY.  TRY AGAIN.")
          ENCODING(ETYPE(MEM).EQ.'ENGLISH')   -->   MASSAGER   ENGLISH
          ENCODING(ETYPE(MEM).EQ.'GPSSPROG')   -->
                   MASSAGER   INTERROGATOR   GPSSPROG
          ENCODING(ETYPE(MEM).EQ.'QUESANSW')   -->
                   MASSAGER(QAMODE(MEM))   INTERROGATOR   COMPMSG
          ENCODING(ETYPE(MEM).EQ.'CHECKIPR')   -->
                   MASSAGER(-QAMODE(MEM))   INTERROGATOR   COMPMSG
          ENCODING   -->   NULL

LEXOLOGY FOR DECODING ENGLISH:
          ADJ('MAXIMUM')  NOUNPH('CONTENT')   -->   NOUNPH('SM')
          ADJ('AVERAGE')  NOUNPH('SR')   -->   NOUNPH('SR')
          ADJ('AVERAGE')  NOUNPH('CONTENT')   -->   NOUNPH('SA')
          ADJ('CURRENT')  NOUNPH('CONTENT')   -->   NOUNPH('S')
          ADJ('AVERAGE')  NOUNPH('TIME')   -->   NOUNPH('ST')
          ADJ('CURRENT')  NOUNPH('LINE')   -->   NOUNPH('Q')
          ADJ('AVERAGE')  NOUNPH('LINE')   -->   NOUNPH('QA')
          ADJ('MAXIMUM')  NOUNPH('LINE')   -->   NOUNPH('QM')
          ADJ('AVERAGE')  VERB('WAIT')  NOUNPH('TIME')   -->   NOUNPH('QT')
          NOUN('MEAN')  NOUN('TRANSIT')  NOUNPH('TIME')   -->   NOUNPH('TB')
          NOUNPH($'GPSSENTY')   -->   STATPH(@8=PRCODE(SUP(NOUNPH)))
          NOUNPH($'ENTITY')  NOUNPH($'GPSSENTY')   -->
                   STATPH(@8=PRCODE(SUP(NOUNPH#2)),@9=IDNO(ENTY(NOUNPH#1)))
          NOUNPH($'STATENTY')   -->   STATPH(@8=5,@9=IDNO(ENTY(NOUNPH)))
          NOUNPH($'MOBENTY')   -->   STATPH(@8=3,@9=IDNO(ENTY(NOUNPH)))
          VERB('PRINT')  STATPH  NOUNPH('STATIST')   -->   PRINTPH(%STATPH)
          NOUNPH(¬PRM,$'GPSSATTR',¬OBJ)  PREPPH('AT')   -->
                   NOUNPH(OBJ(PREPPH))
```

```
MORPHOLOGY FOR DECODING ENGLISH:
          NOUNS('UTILIZA')  T  I  O  N    -->   NOUNS('SR')
          NOUNS('STATIST')  I  C    -->   NCUNS

MCRPHOLOGY FOR ENCODING ENGLISH:
          NOUNS(CHARS(SUP))    -->   NAME(CHARS(SUP(NCUNS)))

DELETE KWDSENT:
SEMOLOGY FOR DECODING ENGLISH:
          KWDSENT(TIMENTY,PROBLEM|RUN|SIMULATE)   -->
                   OK(PRCBTIME(MEM)=TIMENTY(KWDSENT))
          KWDSENT(TIMENTY,TIME,UNIT)   -->   OK(TIMUNIT(MEM)=TIMENTY(KWDSENT))
          KWDSENT(ENGLISH|STATE|DESCRIBE)   -->
                   ENCCDING(ETYPE(MEM)='ENGLISH')
          KWDSENT(PRINT,GPSS,¬PROGRAM)   -->   OK(@8=6,SETIND,SIMOUT)
          KWDSENT(GPSS|VECTOR)   -->
                   ENCODING(ETYPE(MEM)='GPSSPROG',XVSW(MEM),GPSSSW(MEM),
                           ¬GPSS(KWDSENT),-GPSSSW(MEM))
          KWDSENT(RESET)   -->
                   OK(IX=1,XV=2,PUTRX,IX=2,XV=1,PUTRX,SIMULT)
          KWDSENT(CLEAR)   -->
                   OK(IX=1,XV=3,PUTRX,IX=2,XV=1,PUTRX,SIMULT)
          KWDSENT(CONTINUE)   -->
                   OK(IX=1,XV=4,PUTRX,IX=2,XV=1,PUTRX,SIMULT)
          KWDSENT(PERFORM|SIMULATE|RUN)   -->   CK(SIMULT)
          KWDSENT(PRINT,CURRENT,EVENTS)   -->   OK(@8=4,@9=2,SETIND,SIMOUT)
          KWDSENT(PRINT,EVENTS)   -->   OK(@8=4,@9=3,SETIND,SIMOUT)
          KWDSENT(ASK|QUESTICN|PROMPT|INQUIRY)   -->
                   ENCODING(ETYPE(MEM)='QUESANSW')
          KWDSENT(OK|OKAY|COMPLETE|DONE|CHECK)   -->
                   ENCODING(ETYPE(MEM)='CHECKIPR')
          KWDSENT(EXPLAIN|CLARIFY|WHAT|WHICH)   -->
                   ENCODING(ETYPE(MEM)='CHECKIPR')
          KWDSENT(STOP)   -->   OK(-QUESTSW(MEM),-PRED(MEM),-SUCC(MEM),
                                  -CENTY(MEM),-ATTRIB(MEM),-SUPSET(MEM),
                                  -CONDITN(MEM),-QAMODE(MEM))
          KWDSENT   -->   ERROR(MESSAGE2)
          PUNCA/  PRINTPH  PERIOD   -->
                   OK(%PRINTPH,SETIND,SIMOUT,SPARSED(MEM))
:END OF FILE:
```

## LIST OF REFERENCES


1. Minsky, Marvin, ed., Semantic Information Processing, MIT Press, Cambridge, Mass., 1968.

2. Simmons, R. F., "Natural Language Question Answering Systems: 1969", Communications of the ACM, Vol. 13, No. 1, pp. 15-30, January 1970.

3. Lamb, Sydney M., Outline of Stratificational Grammar, Georgetown University Press, Washington, D. C., 1966.

4. Heidorn, George E., Natural Language Inputs to a Simulation Programming System, Technical Report NPS-55HD72101A, Naval Postgraduate School, Monterey, Calif., October 1972.

5. Hansen, Richard D., GES: A Data-Structure-to-GPSS Encoding System, M. S. Thesis, Naval Postgraduate School, Monterey, California, December 1970.

6. McGee, Robert T., The Translation of Data Structure Representations of Simple Queuing Problems into GPSS Programs and English Text, M.S. Thesis, Naval Postgraduate School, Monterey, California, June 1971.

7. Baker, Eldon S., Question-Answer Inputs to a Simulation Program Generating System, M.S. Thesis, Naval Postgraduate School, Monterey, California, June 1971.

8. Hemphill, Frederick H., Computer Verification of the Completeness of a Simulation Problem Description by Natural Language Interaction, M.S. Thesis, Naval Postgraduate School, Monterey, California, December 1971.

9. Williams, Robert J., A GPSS-Like Simulator Callable from a Fortran Program, M.S. Thesis, Naval Postgraduate School, Monterey, California, March 1972.

10. Rickelman, John H., Translation of a Queuing Problem Description Into GPSS-Like Tables, M.S. Thesis, Naval Postgraduate School, Monterey, California, June 1972.

11. International Business Machines Corporation, General Purpose Simulation System/360, User's Manual, 1968.

INITIAL DISTRIBUTION LIST

| | | No. Copies |
|---|---|---|
| 1. | Defense Documentation Center<br>Cameron Station<br>Alexandria, Virginia 22314 | 2 |
| 2. | Library, Code 0212<br>Naval Postgraduate School<br>Monterey, California 93940 | 2 |
| 3. | Professor George E. Heidorn, Code 55Hd<br>Department of Operations Research and<br>Administrative Sciences<br>Naval Postgraduate School<br>Monterey, California 93940 | 5 |
| 4. | Professor David K. Jefferson, Code 53Jf<br>Department of Mathematics<br>Naval Postgraduate School<br>Monterey, California 93940 | 1 |
| 5. | LT Joseph Leon Clapper, USNR<br>Box 19A, R.D.#1<br>Wernersville, Pennsylvania 19565 | 1 |
| 6. | LT Kenneth Stanley Nelson, USN<br>1426 South Gourley<br>Boise, Idaho 83705 | 1 |

Unclassified

Security Classification

# DOCUMENT CONTROL DATA - R & D

(Security classification of title, body of abstract and indexing annotation must be entered when the overall report is classified)

| | |
|---|---|
| 1. ORIGINATING ACTIVITY (Corporate author)<br>Naval Postgraduate School<br>Monterey, California 93940 | 2a. REPORT SECURITY CLASSIFICATION<br>Unclassified<br>2b. GROUP |

3. REPORT TITLE

Towards an English Language Interactive Simulation System

4. DESCRIPTIVE NOTES (Type of report and, inclusive dates)

Master's Thesis; December 1972

5. AUTHOR(S) (First name, middle initial, last name)

Joseph L. Clapper
Kenneth S. Nelson

| 6. REPORT DATE | 7a. TOTAL NO. OF PAGES | 7b. NO. OF REFS |
|---|---|---|
| December 1972 | 111 | 11 |

| | |
|---|---|
| 8a. CONTRACT OR GRANT NO. | 9a. ORIGINATOR'S REPORT NUMBER(S) |
| b. PROJECT NO. | |
| c. | 9b. OTHER REPORT NO(S) (Any other numbers that may be assigned this report) |
| d. | |

10. DISTRIBUTION STATEMENT

Approved for public release; distribution unlimited.

| | |
|---|---|
| 11. SUPPLEMENTARY NOTES | 12. SPONSORING MILITARY ACTIVITY<br>Naval Postgraduate School<br>Monterey, California 93940 |

13. ABSTRACT

Research at the Naval Postgraduate School has led to the development of a system for producing GPSS simulation programs for simple queuing problems through English language dialogue with an IBM 360/67 computer. This thesis describes work done to give the system the capability to actually perform the simulation and report the results through English language dialogue. A complete sample terminal session is included.

| KEY WORDS | LINK A | | LINK B | | LINK C | |
|---|---|---|---|---|---|---|
| | ROLE | WT | ROLE | WT | ROLE | WT |
| Digital Computer Simulation | | | | | | |
| Simulation Programming | | | | | | |
| GPSS | | | | | | |
| Computational Linguistics | | | | | | |
| Grammar-Rule Language | | | | | | |
| Stratificational Grammar | | | | | | |
| Natural Language Processing | | | | | | |

141257

Thesis
C4802 Clapper
c.1 Towards an English
language interactive
simulation system.

Thesis 141257
C4802 Clapper
c.1 Towards an English
language interactive
simulation system.

thesC4802
Towards an English language interactive
3 2768 002 10247 7
DUDLEY KNOX LIBRARY